
Subject: *SOLVED* ETH lost Device problem in VPS with Mandriva
Posted by [xwinner](#) on Sat, 17 Feb 2007 19:15:57 GMT

[View Forum Message](#) <> [Reply to Message](#)

Here is some advance in test and follow a complete detail

take a look at this

when i configure, it's ok, when i stop, lose all eth config, but now i can reconfigure...

```
[root@scrameustache vz]# vzlist
VEID NPROC STATUS IP_ADDR HOSTNAME
101 4 running 192.168.0.101 vps101.localdomain.
[root@scrameustache vz]# vzctl enter 101
entered into VE 101
[root@vps101 /]# ifconfig
venet0 Link encap:UNSPEC HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
inet addr:127.0.0.1 P-t-P:127.0.0.1 Bcast:0.0.0.0 Mask:255.255.255.255
UP BROADCAST POINTOPOINT RUNNING NOARP MTU:1500 Metric:1
RX packets:0 errors:0 dropped:0 overruns:0 frame:0
TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
collisions:0 txqueuelen:0
RX bytes:0 (0.0 b) TX bytes:0 (0.0 b)

venet0:0 Link encap:UNSPEC HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
inet addr:192.168.0.101 P-t-P:192.168.0.101 Bcast:192.168.0.101 Mask:255.255.255.255
UP BROADCAST POINTOPOINT RUNNING NOARP MTU:1500 Metric:1

[root@vps101 /]# ping 192.168.0.1
PING 192.168.0.1 (192.168.0.1) 56(84) bytes of data.
64 bytes from 192.168.0.1: icmp_seq=1 ttl=63 time=37.5 ms
64 bytes from 192.168.0.1: icmp_seq=2 ttl=63 time=0.310 ms

--- 192.168.0.1 ping statistics ---
2 packets transmitted, 2 received, 0% packet loss, time 999ms
rtt min/avg/max/mdev = 0.310/18.947/37.585/18.638 ms
[root@vps101 /]# exit
logout
exited from VE 101
[root@scrameustache vz]# vzctl set 101 --netif_add
eth0,00:12:34:56:78:9A,veth101.0,00:12:34:56:78:9B --save
Configure veth devices: veth101.0
Saved parameters for VE 101
[root@scrameustache vz]# ifconfig veth101.0 0
[root@scrameustache vz]# echo 1 > /proc/sys/net/ipv4/conf/veth101.0/forwarding
[root@scrameustache vz]# echo 1 > /proc/sys/net/ipv4/conf/veth101.0/proxy_arp
[root@scrameustache vz]# echo 1 > /proc/sys/net/ipv4/conf/eth0/forwarding
[root@scrameustache vz]# echo 1 > /proc/sys/net/ipv4/conf/eth0/proxy_arp
[root@scrameustache vz]# vzctl enter 101
```

```
entered into VE 101
[root@vps101 /]# /sbin/ifconfig eth0 0
[root@vps101 /]# /sbin/ip addr add 192.168.0.101 dev eth0
[root@vps101 /]# /sbin/ip route add default dev eth0
RTNETLINK answers: File exists
[root@vps101 /]#
[root@vps101 /]# exit
logout
exited from VE 101
[root@scrameustache vz]# ip route add 192.168.0.101 dev veth101.0
RTNETLINK answers: File exists
[root@scrameustache vz]#
[root@scrameustache vz]# vzctl restart 101
Restarting VE
Stopping VE ...
VE was stopped
VE is unmounted
Starting VE ...
VE is mounted
Adding IP address(es): 192.168.0.101
Setting CPU units: 1000
Set hostname: vps101.localdomain.
File resolv.conf was modified
Configure veth devices: veth101.0
VE start in progress...
[root@scrameustache vz]# vzctl enter 101
entered into VE 101
[root@vps101 /]# ifconfig
lo Link encap:Local Loopback
inet addr:127.0.0.1 Mask:255.0.0.0
      UP LOOPBACK RUNNING MTU:16436 Metric:1
      RX packets:0 errors:0 dropped:0 overruns:0 frame:0
      TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
      collisions:0 txqueuelen:0
      RX bytes:0 (0.0 b) TX bytes:0 (0.0 b)

[root@vps101 /]#[root@vps101 /]# exit
logout
exited from VE 101
[root@scrameustache vz]# vzctl stop 101
Stopping VE ...
VE was stopped
VE is unmounted
[root@scrameustache vz]# cd /etc/rc.d/init.d/
[root@scrameustache init.d]# ./vz restart
Stopping OpenVZ: [ OK ]
Starting OpenVZ: [ OK ]
Bringing up interface venet0: [ OK ]
```

```
Configuring interface venet0: [ OK ]
Configure node UB resources: [ OK ]
Starting VE 101: [ OK ]
[root@scrameustache init.d]# vzctl enter 101
entered into VE 101
[root@vps101 /]# ifconfig
lo Link encap:Local Loopback
inet addr:127.0.0.1 Mask:255.0.0.0
      UP LOOPBACK RUNNING MTU:16436 Metric:1
      RX packets:0 errors:0 dropped:0 overruns:0 frame:0
      TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
      collisions:0 txqueuelen:0
      RX bytes:0 (0.0 b) TX bytes:0 (0.0 b)

[root@vps101 /]# exit
logout
exited from VE 101
[root@scrameustache init.d]# vzctl set 101 --netif_add
veth101,00:12:34:56:78:9A,eth0.0,00:12:34:56:78:9B --save
Configure veth devices: eth0.0
Saved parameters for VE 101
[root@scrameustache init.d]# ifconfig veth101.0 0
[root@scrameustache init.d]# echo 1 > /proc/sys/net/ipv4/conf/veth101.0/forwarding
[root@scrameustache init.d]# echo 1 > /proc/sys/net/ipv4/conf/veth101.0/proxy_arp
[root@scrameustache init.d]# echo 1 > /proc/sys/net/ipv4/conf/eth0/forwarding
[root@scrameustache init.d]# echo 1 > /proc/sys/net/ipv4/conf/eth0/proxy_arp
[root@scrameustache init.d]# vzctl enter 101
entered into VE 101
[root@vps101 /]# /sbin/ifconfig eth0 0
[root@vps101 /]# /sbin/ip addr add 192.168.0.101 dev eth0
[root@vps101 /]# /sbin/ip route add default dev eth0
[root@vps101 /]# exit
logout
exited from VE 101
[root@scrameustache init.d]# ip route add 192.168.0.101 dev veth101.0
RTNETLINK answers: File exists
[root@scrameustache init.d]# ip route add 192.168.0.101 dev veth101.0 --save
Error: either "to" is duplicate, or "--save" is a garbage.
[root@scrameustache init.d]# vzctl enter 101
entered into VE 101
[root@vps101 /]# ifconfig
eth0 Link encap:Ethernet HWaddr 00:12:34:56:78:9A
inet addr:192.168.0.101 Bcast:0.0.0.0 Mask:255.255.255.255
      UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
      RX packets:0 errors:0 dropped:0 overruns:0 frame:0
      TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
      collisions:0 txqueuelen:0
      RX bytes:0 (0.0 b) TX bytes:0 (0.0 b)
```

```
lo Link encap:Local Loopback  
inet addr:127.0.0.1 Mask:255.0.0.0  
      UP LOOPBACK RUNNING MTU:16436 Metric:1  
      RX packets:0 errors:0 dropped:0 overruns:0 frame:0  
      TX packets:0 errors:0 dropped:0 overruns:0 carrier:0  
      collisions:0 txqueuelen:0  
      RX bytes:0 (0.0 b) TX bytes:0 (0.0 b)
```

```
[root@vps101 /]# exit  
logout
```

SOME suggest to conserve configuration ?

Thanks a lot,

André
