
Subject: Re: Can't use IPTables inside a VE, here iptable_nat

Posted by [curx](#) on Wed, 11 Apr 2007 12:16:08 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi,

kernel iptables_nat module is loaded in VE0 (HN) ...?

```
VE0_# lsmod | grep ^iptables_nat
```

when not load it:

```
VE0_# modprobe iptable_nat
```

enable iptable_nat in VE

```
VE0_# vzctl set <VEID> --iptables iptable_nat --save
```

restart your VE

```
VE0_# vzctl restart <VEID>
```

check it

```
VE0_# vzctl exec <VEID> iptables -t nat -L -v --line-number
```
