

---

Subject: Re: /dev/tty0  
Posted by [Jun OKAJIMA](#) on Thu, 07 Jun 2007 15:17:41 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Ummm?? Maybe here is the problem? What is ve\_is\_super()???

```
@@ -2506,6 +2603,12 @@ retry_open:
#ifdef CONFIG_VT
    if (device == MKDEV(TTY_MAJOR,0)) {
        extern struct tty_driver *console_driver;
+ #ifdef CONFIG_VE
+ if (!ve_is_super(get_exec_env())) {
+ mutex_unlock(&tty_mutex);
+ return -ENODEV;
+ }
+ #endif
        driver = console_driver;
        index = fg_console;
```

-----

I still have not solved this issue.  
You change something on /dev/tty[0-9] in a VE?  
I guess they are not same as usual ones.

-----

I can not open /dev/tty0.  
"DEVICES="c:4:all:rw" does not help.

/dev/tty works, but /dev/tty0 does not.  
This is feature? or possible to solve this?  
It is Okay to run Apache/Sendmail,  
but a bit inconvenient for debugging or development or such purposes.

OpenVZ version: 2.6.18-028stab033

--- Okajima, Jun. Tokyo, Japan.

```
[ If you dont add "DEVICES=c:4:all:rw" line to vps.conf ]
# cat /dev/tty0
cat: /dev/tty0: Permission denied
[ If you add "DEVICES=" to vps.conf ]
# cat /dev/tty0
cat: /dev/tty0: No such device
( anyway, you can not access /dev/tty0. Why? This is inevitable feature? )
# ls -la /dev/tty0
crw----- 1 root tty 4, 0 May  6 11:39 /dev/tty0
```

```
# uname -r  
2.6.18-028stab033
```

---