

---

Subject: **\*SOLVED\*** iptables state in VE broken  
Posted by [dlzinc](#) on Sat, 30 Jun 2007 00:56:15 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

```
uname -r  
2.6.18-8.1.4.el5.028stab035.1
```

Host is CentOS 5 x86\_64  
VE is also CentOS 5 x86\_64

If I do:  
iptables -F  
iptables -A INPUT -m state --state NEW,ESTABLISHED,RELATED -j ACCEPT  
iptables -P DROP

I would expect to be able to SSH into this VE, however I can't. Using vzctl enter, I saw the counters for DROP incremented and the single iptables line counter is still 0. There also is no /proc/net/ip\_conntrack present inside the VE.

IPTABLES (in the ve .conf file) is not set, all other modules appear to work (e.g. ipt\_owner)

conntrack is loaded on the HN and was loaded before the VE was started. Any ideas? or bug...

Oddly enough, I have another box:  
2.6.18-8.1.4.el5.028stab035.1  
Host is CentOS 4 x86\_64  
VE is also CentOS 4 i686

state tracking works properly (and there's a /proc/net/ip\_conntrack in the VE)

---