

---

Subject: Re: Running X server in VE

Posted by [tabaki](#) on Sun, 05 Aug 2007 10:16:03 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

in fedora-6 (centos-5) VE:

I install Xvnc-server. Running Xvnc server over GDM.

```
vzyum XXX install yum
```

```
vzyum XXX install gdm
```

may be installing by dependence udev, it`s very bad, need remove it

```
vzrpm XXX -e udev module-init-tools mkinitrd --nodeps
```

```
vzrpm XXX -ihv vzdev-xxx.rpm --nodeps
```

```
vzrpm XXX -ihv dummy-xxx.rpm --nodeps
```

Login in VE.

```
yum install vnc-server xorg-x11-fonts*
```

If need KDE or GNOME:

```
yum groupinstall "GNOME Desktop Environment"
```

or

```
yum groupinstall "KDE (K Desktop Environment)"
```

Modification file /etc/gdm/custom.conf for starting Xvnc server on display 0:

```
init 5
```

If not OK, need increase limits UBC-resources, see failcnt.

```
cat /proc/user_beancounters
```

Connect to VE trough VNC-client (on Windows or Linux)

Sorry for my english.

---