
Subject: [S390] update fs3270 to use a struct pid
Posted by [Cedric Le Goater](#) on Tue, 12 Sep 2006 13:42:45 GMT
[View Forum Message](#) <> [Reply to Message](#)

this patch replaces the pid_t value with a struct pid to avoid pid wrap around problems.

Signed-off-by: Cedric Le Goater <clg@fr.ibm.com>
Cc: Martin Schwidefsky <schwidefsky@de.ibm.com>
Cc: Eric W. Biederman <ebiederm@xmission.com>
Cc: containers@lists.osdl.org

drivers/s390/char/fs3270.c | 11 ++++++-----
1 file changed, 6 insertions(+), 5 deletions(-)

Index: 2.6.18-rc6/drivers/s390/char/fs3270.c

=====

--- 2.6.18-rc6.orig/drivers/s390/char/fs3270.c
+++ 2.6.18-rc6/drivers/s390/char/fs3270.c
@@ -28,7 +28,7 @@ struct raw3270_fn fs3270_fn;

```
struct fs3270 {
    struct raw3270_view view;
- pid_t fs_pid; /* Pid of controlling program. */
+ struct pid* fs_pid; /* Pid of controlling program. */
    int read_command; /* ccw command to use for reads. */
    int write_command; /* ccw command to use for writes. */
    int attention; /* Got attention. */
@@ -103,7 +103,7 @@ fs3270_restore_callback(struct raw3270_r
    fp = (struct fs3270 *) rq->view;
    if (rq->rc != 0 || rq->rescnt != 0) {
        if (fp->fs_pid)
- kill_proc(fp->fs_pid, SIGHUP, 1);
+ kill_pid(fp->fs_pid, SIGHUP, 1);
    }
    fp->rdbuf_size = 0;
    raw3270_request_reset(rq);
@@ -174,7 +174,7 @@ fs3270_save_callback(struct raw3270_requ
    */
    if (rq->rc != 0 || rq->rescnt == 0) {
        if (fp->fs_pid)
- kill_proc(fp->fs_pid, SIGHUP, 1);
+ kill_pid(fp->fs_pid, SIGHUP, 1);
        fp->rdbuf_size = 0;
    } else
        fp->rdbuf_size = fp->rdbuf->size - rq->rescnt;
@@ -443,7 +443,7 @@ fs3270_open(struct inode *inode, struct
```

```

return PTR_ERR(fp);

init_waitqueue_head(&fp->wait);
- fp->fs_pid = current->pid;
+ fp->fs_pid = get_pid(task_pid(current));
rc = raw3270_add_view(&fp->view, &fs3270_fn, minor);
if (rc) {
    fs3270_free_view(&fp->view);
@@ -481,7 +481,8 @@ fs3270_close(struct inode *inode, struct
    fp = filp->private_data;
    filp->private_data = NULL;
    if (fp) {
- fp->fs_pid = 0;
+ put_pid(fp->fs_pid);
+ fp->fs_pid = NULL;
    raw3270_reset(&fp->view);
    raw3270_put_view(&fp->view);
    raw3270_del_view(&fp->view);

```

Containers mailing list

Containers@lists.osdl.org

<https://lists.osdl.org/mailman/listinfo/containers>
