
Subject: Re: howto auto add VE veth to a HN bridge upon VE startup?

Posted by [khorenko](#) on Thu, 13 Sep 2007 13:30:13 GMT

[View Forum Message](#) <> [Reply to Message](#)

ok, i have good news for you.

When you add a veth device to the bridge manually it (veth101.0 interface) is already in the UP state.

At the same time when the script /etc/vz/veth.bridge.addif runs veth101.0 is still down cause avahi-daemon hasn't brought it UP yet. Thus brctl adds downed interface into the bridge and that's why veth doesn't work.

To correct this it's enough to add a line to the /etc/vz/veth.bridge.addif:

```
if [ ! -n "$VZHOSTIF" ]; then
    echo "According to $CONFIGFILE VE$VEID has no veth interface configured."
    exit 1
fi
```

```
+ ifconfig veth${VEID}.0 0
  brctl addif dmzbr0 veth${VEID}.0
  exit $?
```
