

---

Subject: Re: difference between /vz/private/ and /vz/root/ ? [Solved]

Posted by [piavlo](#) on Thu, 22 Nov 2007 09:56:25 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

If you want to share gentoo portage tree for you VEs with HN

then you can simply bind mount it

```
>cat /etc/vz/bin/mount-portage
```

```
#!/bin/bash
```

```
mount -n --bind /usr/portage /vz/root/${VEID}/usr/portage
```

```
exit ${?}
```

```
>chmod 700 /etc/vz/bin/mount-portage
```

now symlink the VE id you want to have portage in

```
>cd /etc/vz/conf
```

```
>ln -snf /etc/vz/bin/mount-portage 105.mount
```

Next time you start the VE it will auto bind mount /usr/portage from HN

---