## Subject: Re: live migration with extra mounts in VE Posted by frodo on Mon, 03 Dec 2007 13:31:44 GMT

View Forum Message <> Reply to Message

Hey Vasily,

The output of the vzmigrate command:

(dumping seems to work fine, undumping on the other node produces an error, in bold)

[root@sv-ard-drp8 dev]# vzmigrate -r no -v --online 192.168.254.30 120 OPT:-r

OPT:-v

**OPT:--online** 

OPT:192.168.254.30

Starting online migration of VE 120 on 192.168.254.30

OpenVZ is running...

Loading /etc/vz/vz.conf and /etc/vz/conf/120.conf files

Check IPs on destination node:

Preparing remote node

Copying config file

120.conf 100% 1933 1.9KB/s 00:00

Saved parameters for VE 120

Creating remote VE root dir

Creating remote VE private dir

Initializing remote quota

Quota init

Turning remote quota on

Syncing private

Live migrating VE

Suspending VE

Setting up checkpoint...

suspend...

get context...

Checkpointing completed succesfully

Dumping VE

Setting up checkpoint...

join context..

dump...

Checkpointing completed succesfully

Copying dumpfile

dump.120 100% 1581KB 1.5MB/s 00:00

Syncing private (2nd pass)

Syncing 2nd level quota

Dumping 2nd level quota

Copying 2nd level quota

quotadump.120 100% 21 0.0KB/s 00:00

Load 2nd level quota

Undumping VE

Restoring VE ...
Starting VE ...

vzquota: (warning) Quota is running for id 120 already

VE is mounted undump...

Setting CPU units: 1000

Setting devices

Configure meminfo: 49152

Configure veth devices: veth120.0

Initializing interface veth120.0 for VE120. Adding interface veth120.0 to the bridge br1. Error: undump failed: No such file or directory

Restoring failed:

-2 mounting /data/ftp ext3 40000000

rst\_namespace: -2 VE start failed Stopping VE ... VE was stopped VE is unmounted

Error: Failed to undump VE

Resuming...

vzquota: (error) Quota is not running for id 120

[root@sv-ard-drp8 dev]#

The dmesg output on the remote node gives me these error messages:

CPT ERR: df8a3800,120 :- 2 mounting /data/ftp ext3 40000000

CPT ERR: df8a3800,120 :rst namespace: -2

I am working with a logical volume created with lvm2. This logical volume is visible on both nodes (I can mount it simultaneously on both nodes, which is very dangerous, i know

I have the following in my <VEID>.conf for this volume:

DEVNODES="sda:rw mapper/vg 120-lv ftpdata:rw"

sda is the iscsi LUN that is shared between the nodes, and which contains the logical volume.

Regards,

frodo