Subject: Re: init output Posted by rkagan on Tue, 11 Dec 2007 14:29:37 GMT View Forum Message <> Reply to Message

On Tue, Dec 11, 2007 at 01:51:30PM +0100, Dietmar Maurer wrote:

>

> > tail: /var/lib/vz/root/777/var/log/init.log: file truncated

> >

- > > Any idea why? I already searched the sysvinit code sources,
- > > but found nothing there.

>

- > 'vzctl stop' does not work at all with my modified init no processes
- > killed.

vzctl stop effectively calls 'init 0'. Now that /sbin/init is your script, it unconditionally truncates the log file, and then calls /sbin/init.orig again without arguments.

To get what you want you need a slightly more elaborate script, something like the following (untested):

#!/bin/sh

file must be there - create it if we're pid 1 [\$\$ = 1] && echo >/var/log/init.log export CONSOLE=/var/log/init.log exec /sbin/init.org "\$@"

That said, I do think we need to implement some sort of serial console-like device for VEs. We'll see what can be done here.

Roman.