

---

Subject: Re: Debian host, Ubuntu VE won't start  
Posted by [maratrus](#) on Wed, 02 Apr 2008 07:40:18 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Hi,

I'm terribly sorry for delay.  
The reason is in the following:

During the startup in /vz/private/VE\_ID/etc/S35mountall.sh there is a such string:  
kill -USR1 1

From "man 2 kill"

Quote:

The only signals that can be sent task number one, the init process, are those for which init has explicitly installed signal handlers. This is done to assure the system is not brought down accidentally.

This logic was broken down in old kernels. See  
[http://bugzilla.openvz.org/show\\_bug.cgi?id=533](http://bugzilla.openvz.org/show_bug.cgi?id=533)  
The problem was fixed in 2.6.18 kernels.

There are several workarounds in your case:

1. If it is possible use the latest 2.6.18 kernel.
2. try to comment "kill -USR1 1" string in the script mentioned above.

Thank You very much!

---