
Subject: Re: Re: can access vps from server not from network
Posted by [kir](#) on Tue, 16 May 2006 20:35:10 GMT

[View Forum Message](#) <> [Reply to Message](#)

(1) From inside VE, you do not need to configure any sysctl parameters.

(2) Probably the reason why you can not reach any hosts from inside VE is you forgot to set VE's nameserver. Please do the following:

a. on the host system, check your nameserver(s) IP address(es):

```
# grep nameserver /etc/hosts
```

It should print one or more lines in the form

```
nameserver x.x.x.x
```

where x.x.x.x is an IP address.

b. Set that (those) address(es) to be VE's nameserver(s):

```
# vzctl set VEID --nameserver x.x.x.x [--nameserver y.y.y.y] --save
```

In fact, just one nameserver should be sufficient.

(3) For the next time, please provide more details. Here you wrote:

> cannot ping or wget anyfile while inside the VPS.

It would be great to show some examples here. Say, if nameserver is not set, the error from ping or wget would be like "Temporary failure in name resolution" or "Unable to resolve hostname xxxx.tld". Since you do not give details here, we have to guess.

Regards,
Kir.

abhishek jain wrote:

>>>On Tue, May 16, 2006 at 08:08:14AM +0530, abhishek jain wrote:

>>> Hi,

>> >I add vps via the process listed at quick install guide, i can

> access the

>>> vps via the server on which it is hosted , but when accessing from

> outside

>>> using the assigned IP i access the server and not the VPS.

>>> I can see the ip assigned to VPS in /sbin/ifconfig of the server.

>

>>Make sure

>>

>># sysctl net.ipv4.ip_forward

>>

>>prints 1. If it doesn't, set it with

>

>># sysctl net.ipv4.ip_forward=1

>
>>To have it set on every boot you need to tweak a config file depending
>>on the distro you're using. E.g. for RedHat-based distros (RHEL,
>>Fedora, CentOS) this is /etc/sysctl.conf.
>>
>>IIRC this is mentioned in the installation guide.
>
>>Roman.
>
> hi,
> Actually the problem solved by deleting the IP from the main system.
> Now another problem arised that i can access the VPS from outside but
> cannot ping or wget anyfile while inside the VPS.
> I see the document and it was written
>
>
> I did this both on the VPS and in the Server still no result.
>
> Also i get the following error when i start the network while inside
> the VPS :
>
> [root@server ~]# /etc/init.d/network restart
> Shutting down interface venet0: [OK]
> Shutting down loopback interface: [OK]
> Setting network parameters: net.ipv4.ip_forward = 0
> error: unknown error 1 setting key 'net.ipv4.conf.default.rp_filter'
> error: unknown error 1 setting key
> 'net.ipv4.conf.default.accept_source_route'
> error: unknown error 1 setting key 'kernel.sysrq'
> error: unknown error 1 setting key 'kernel.core_uses_pid'
> [FAILED]
> Bringing up loopback interface: [OK]
> Bringing up interface venet0: [OK]
>
> This Failed line appears.
>
> Pl. help,
> Thanks,
> Abhishek jain
>
> -----
>
