
Subject: VLAN not working in VE? <SOLVED>
Posted by [januszzz](#) on Mon, 13 Oct 2008 12:23:38 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hi,

I got 2 interfaces on HE and wanted one for management and the second for VE's (I need several VLANs there).

So I setup HE interfaces like this (fat trimmed)

```
eth0    Link encap:Ethernet HWaddr 00:21:5e:26:b3:cc
        inet addr:126.66.64.151 Bcast:126.66.65.255 Mask:255.255.254.0

eth1    Link encap:Ethernet HWaddr 00:21:5e:26:b3:ce
        inet6 addr: fe80::221:5eff:fe26:b3ce/64 Scope:Link
eth1.20  Link encap:Ethernet HWaddr 00:21:5e:26:b3:ce
        inet6 addr: fe80::221:5eff:fe26:b3ce/64 Scope:Link

eth1.980 Link encap:Ethernet HWaddr 00:21:5e:26:b3:ce
        inet6 addr: fe80::221:5eff:fe26:b3ce/64 Scope:Link

venet0  Link encap:UNSPEC HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
        UP BROADCAST POINTOPOINT RUNNING NOARP MTU:1500 Metric:1
        RX packets:0 errors:0 dropped:0 overruns:0 frame:0
        TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:0
        RX bytes:0 (0.0 B) TX bytes:0 (0.0 B)
```

(lo, sit0, other VLANs ommitted).

Then I added the vlan to VE like this:

```
vzctl set 110 --netif_add vlan980 --save
```

Then I setup the VE settings like this:

```
(snippet from 110.conf)
IP_ADDRESS="10.0.0.2"
NETIF="    ifname=vlan980,mac=00:18:51:F6:CD:87,host_ifname=veth110.980
,host_mac=00:18:51:70:E9:7F "
```

And the problem is I still cannot access the other ip on the network (PING 10.0.0.1 (10.0.0.1) 56(84) bytes of data.

From 10.0.0.2 icmp_seq=1 Destination Host Unreachable)! How to debug this??

BTW. when I assign an address from the VLAN to eth1.980 on HN it works, but VE - its not.

Thanks!
