
Subject: Re: Invalid Kernel: FC6 Guest + Asterisk, FC10 Host

Posted by [sjdean](#) on Tue, 24 Mar 2009 22:52:55 GMT

[View Forum Message](#) <> [Reply to Message](#)

Still got the same problems with the Fedora Core 6 container I copied from a physical host.

I've installed a CentOS 5 container template from OpenVZ which works fine.

I've gone through the entire /dev of the CentOS 5 Container (102) and copied to my Fedora Core 6 Container (101) without any joy.

The last few lines of the strace -ff are:

```
[pid 19341] ioctl(4, 0x400c2e05, 0xbfacebd0) = 101
[pid 19341] setgroups32(0, []) = 0
[pid 19341] close(4) = 0
[pid 19341] open("/dev/ptmx", O_RDWR) = -1 ENOENT (No such file or directory)
[pid 19341] open("/dev/pty0", O_RDWR) = -1 ENOENT (No such file or directory)
[pid 19341] write(2, "Unable to open pty", 18) = 18
[pid 19341] write(2, ": No such file or directory", 27) = 27
[pid 19341] write(2, "\n", 1) = 1
[pid 19341] write(9, "\377\377\377\377", 4) = 4
[pid 19340] <... read resumed> "\377\377\377\377", 4) = 4
[pid 19340] fstat64(1, {st_mode=S_IFCHR|0620, st_rdev=makedev(136, 1), ...}) = 0
[pid 19340] mmap2(NULL, 4096, PROT_READ|PROT_WRITE,
MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) = 0xb7f97000
[pid 19340] write(1, "enter into CT 101 failed\n", 25enter into CT 101 failed
) = 25
[pid 19340] fcntl64(6, F_GETFL) = 0 (flags O_RDONLY)
[pid 19340] fcntl64(6, F_SETFL, O_RDONLY|O_NONBLOCK) = 0
[pid 19340] read(6, "Unable to open pty: No such file"..., 10239) = 46
[pid 19340] write(1, "Unable to open pty: No such file"..., 46Unable to open pty: No such file or
directory
) = 46
[pid 19340] read(6, 0xbface3e0, 10239) = -1 EAGAIN (Resource temporarily unavailable)
```

I've checked rc.sysinit on both, and both have the udev start line:

rc.sysinit has udev started on both

rc.sysinit:/sbin/start_udev

/etc/udev/makedev.d/50-udev.nodes shows the following on 101:

```
tty1
tty2
tty3
```

tty4
tty5
tty6
loop0
loop1
loop2
loop3
loop4
loop5
loop6
loop7
parport0
parport1
parport2
parport3
net/tun
ppp
console
null
zero

while the Working system, 102, shows:

loop0
loop1
loop2
loop3
loop4
loop5
loop6
loop7
parport0
parport1
parport2
parport3
net/tun
ppp
console
null
zero

user_beancounters show:

uid	resource	held	maxheld	barrier	limit	failcnt	
102:	kmemsize	934718	1315837	11055923	11377049		0
	lockedpages	0	0	256	256	0	
	privvmpages	3332	7240	65536	69632	0	
	shmpages	31	31	21504	21504	0	

dummy	0	0	0	0	0	
numproc	12	18	240	240	0	
physpages	1940	2559	0	2147483647	0	
vmguarpages	0	0	33792	2147483647	0	
oomguarpages	1940	2559	26112	2147483647	0	
numtcpsock	4	4	360	360	0	
numflock	5	7	188	206	0	
numpty	0	0	16	16	0	
numsiginfo	0	2	256	256	0	
tcpsndbuf	35776	0	1720320	2703360	0	
tcprcvbuf	65536	0	1720320	2703360	0	
othersockbuf	6708	8620	1126080	2097152	0	
dgramrcvbuf	0	8380	262144	262144	0	
numothersock	9	11	360	360	0	
dcachesize	0	0	3409920	3624960	0	
numfile	433	584	9312	9312	0	
dummy	0	0	0	0	0	
dummy	0	0	0	0	0	
dummy	0	0	0	0	0	
numiptent	10	10	128	128	0	
101: kmemsize	3867358	4067179	11055923	11377049	0	
lockedpages	0	0	256	384	0	
privvmpages	62330	62783	65536	69632	0	
shmpages	173	173	21504	21504	0	
dummy	0	0	0	0	0	
numproc	56	61	240	240	0	
physpages	14200	14800	0	2147483647	0	
vmguarpages	0	0	33792	2147483647	0	
oomguarpages	14200	14800	26112	2147483647	0	
numtcpsock	16	17	360	360	0	
numflock	8	10	188	206	0	
numpty	0	1	16	16	0	
numsiginfo	1	4	256	256	0	
tcpsndbuf	143104	0	1720320	2703360	0	
tcprcvbuf	212992	0	1720320	2703360	0	
othersockbuf	64144	72492	1126080	2097152	0	
dgramrcvbuf	0	8380	262144	262144	0	
numothersock	46	50	360	360	0	
dcachesize	0	0	3409920	3624960	0	
numfile	1430	1491	9312	9312	0	
dummy	0	0	0	0	0	
dummy	0	0	0	0	0	
dummy	0	0	0	0	0	
numiptent	10	10	128	128	0	

While the dev folder on 101 contains:

```
[root@localhost dev]# dir
console mem  ptya1 ptya8 ptyaf ptyp6 ptypd  random ttya3 ttyaa ttyp1 ttyp8 ttypf
core  null  ptya2 ptya9 ptyp0 ptyp7 ptype  stderr ttya4 ttyab ttyp2 ttyp9 urandom
fd    port  ptya3 ptyaa ptyp1 ptyp8 ptypf  stdin  ttya5 ttyac ttyp3 ttypa zero
full  ptmc  ptya4 ptyab ptyp2 ptyp9 ram    stdout ttya6 ttyad ttyp4 ttypb
initctl ptmx  ptya5 ptyac ptyp3 ptypa ram0  ttya0  ttya7 ttyae ttyp5 ttypc
kmem  pts  ptya6 ptyad ptyp4 ptypb ram1  ttya1  ttya8 ttyaf ttyp6 ttypd
kmsg  ptya0 ptya7 ptyae ptyp5 ptypc ramdisk ttya2  ttya9 ttyp0 ttyp7 ttype
```

The container cannot be entered if I simply do this from outside the container:

```
/sbin/MAKEDEV -d /vz/private/123/dev ttyp ptyp
```

But I can do this:

```
vzctl exec 101 /sbin/MAKEDEV tty
vzctl exec 101 /sbin/MAKEDEV pty
vzctl enter 101
```

At this stage, I'm thinking... Memory?

Cheers
Simon
