## Subject: Re: NTP Server in einer virtuellen Umgebung - SOLVED Posted by MailingListe on Tue, 13 Dec 2011 08:44:48 GMT

View Forum Message <> Reply to Message

Zitat von Daniel Bauer <mlist@dsb-gmbh.de>:

```
> From: <lst hoe02@kwsoft.de>
>> Zitat von Daniel Bauer <mlist@dsb-gmbh.de>:
>>
>>> From: <lst hoe02@kwsoft.de>
>>>> Zitat von Daniel Pittman <daniel@rimspace.net>:
>>>> On Sun, Dec 11, 2011 at 07:09, Daniel Bauer <mlist@dsb-gmbh.de>
>>>> wrote:
>>>>
>>>>> I've a VPS for my internal LAN, which should also be used as a NTP
>>>> server.
>>>>> The HN has already syncronized the time by de.pool.ntp.org, so the
>>>>> time is
>>>>> also ok inside the VPS.
>>>>> The NTP server inside the VPS stalled, ntpg -p shows:
>>>>
>>>> You don't need NTP inside the container, just on the HN. The VE
>>>> can't
>>>> set the time anyhow.
>>>>
>>>> Not really true. You need special capabilities assigned to the VE to
>>>> let it manage your system clock. So if you need ntp inside the VE you
>>> should do something like "vzctl set <VEID> --capability sys time:on",
>>>> install ntp inside the VE and deinstall it on the HN.
>>>
>>> But that's not what I want.
>>>
>>> I want the HN to be a NTP client, so that all (HN + VE) have a valid
>>> time.
>>> This works already.
>>> I want the VE to be a NTP server for the local LAN, without beeing a
>>> NTP Client.
>>> That doesn't work.
>>
>> NTP by default only works as server if it has a valid timesource. By
>> default it does not use the "local clock" because its unreliable. On
>> the other hand NTP always try to adjust the local clock if it has a
>> valid timesource. This does not work in a VE if you don't set the
>> capability to adjust the clock, NTP will even run as "root" if it is
>> not able to adjust the local clock with the intended user.
```

>>

- >> If you insist on your network design your options are:
- >> Let the VE NTP get the time from the HN and let it run as root on the
- >> VE
- >> Try to hack NTP use the local clock as timesource and not try to
- >> update

- > the solution was not to take localhost, but
- >> server 127.127.1.0
- >> fudge 127.127.1.0 stratum 12
- > now it works.

But be aware that NTP inside the VE is running as "root" in this case. Don't every expose it to untrusted networks this way.

Regards

Andreas

## File Attachments

1) smime.p7s, downloaded 463 times