

---

Subject: CT starts in vz init, even if stopped before and disabled.

Posted by [JAlbstmeijer](#) on Wed, 07 Nov 2012 20:15:05 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hi,

running:

2.6.32-042stab063.2

vzctl-4.1-1

vzctl-core-4.1-1

CT starts with vz init even if state was stopped and ONBOOT=no for that CT

ik looks like

```
vzlist -aH -octid -s-bootorder $velist
```

in /etc/init.d/vz returns my CT when \$velist is empty

```
+ need_restart=
++ ls /var/lib/vzctl/vzreboot
++ awk '$2 == "yes" {print $1}'
++ vzlist -aH -octid,onboot
+ velist=
++ vzlist -aH -octid -s-bootorder
+ velist=101
+ sysctl -q -w net.ipv4.route.src_check=0
+ for veid in '$velist'
+ '[' 101 = 0 ']'
+ __echo 'Starting CT 101: '
+ '[' redhat = redhat ']'
+ echo -n 'Starting CT 101: '
```

Thank you.

---