Subject: IPTables Modules not loading on Boot, although /etc/sysconfig/iptables-config is correct Posted by MikeDVB on Wed, 14 Nov 2012 10:44:24 GMT View Forum Message <> Reply to Message

I've run into a bit of a strange issue, I'm not sure if it's a bug so I'm looking for some general information at this point.

Linux redacted.redacted.com 2.6.18-308.8.2.el5.028stab101.1 #1 SMP Sun Jun 24 20:25:35 MSD 2012 x86 64 x86 64 x86 64 GNU/Linux

vzctl-4.1-1 vzctl-core-4.1-1 vzctl-core-4.1-1 ovzkernel-devel-2.6.18-308.8.2.el5.028stab101.1 vzquota-3.1-1 ovzkernel-2.6.18-308.8.2.el5.028stab101.1

The IPTABLES\_MODULES line from the /etc/sysconfig/iptables-config is: IPTABLES\_MODULES="ipt\_REJECT ipt\_tos ipt\_TOS ipt\_LOG ip\_conntrack ipt\_limit ipt\_multiport iptable\_filter iptable\_mangle ipt\_TCPMSS ipt\_tcpmss ipt\_ttl ipt\_length ipt\_state iptable\_nat ip\_nat\_ftp ipt\_owner ipt\_REDIRECT"

When the node boots up, just about every VPS is unreachable from outside the node. If I modprobe all of those modules above, and then restart a VPS I am able to reach it as expected. The same modules are also listed in /etc/vz/vz.conf

My current fix for this is a bit of a kludge - I've disabled the vz service on boot, and then I modprobe those modules followed by service vz start in the /etc/rc.local

If I have a configuration file issue somewhere, ideally I'd just like to fix it and document the issue so others in the future can readily fix the issue. If this is an OpenVZ / Kernel bug - then I'll file the necessary report but don't want to 'jump the gun' on that.

If you need any information at all that isn't provided, let me know.