
Subject: CentOS 7 telnet-server issue

Posted by [seneca214](#) on Fri, 13 Nov 2015 14:59:40 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hello,

We're seeing the following issues with the telnet-server package in CentOS 7 running in a openvz container (in proxmox 3.4). We only see this when running in a openvz container, i.e. not with CentOS 7 install on a physical server, or a LXC container. When logging into the server via telnet, characters are missing from the login prompt, text is not echoed back, and new lines on the screen are 'stair-stepping'. Has anyone run across this before? Any suggestions for making this work correctly? We see this happen when using a telnet client from the localhost, putty on windows and from telnet on other devices on the network.

In addition:

* In CentOS 7. If you edit the `/usr/lib/systemd/system/telnet@.service` file changing `ExecStart` to be `ExecStart=-/usr/sbin/in.telnetd -D options`, telnets to the server work, however you're left with initial debugging information on the screen. Not ideal. e.g.

```
$ telnet localhost
Trying 127.0.0.1...
Connected to localhost.
Escape character is '^]'.
td: send do TERMINAL TYPE
td: send do TSPEED
td: send do XDISPLOC
td: send do NEW-ENVIRON
td: rcv do SUPPRESS GO AHEAD
td: send will SUPPRESS GO AHEAD
td: rcv will TERMINAL TYPE
td: rcv will NAWS
td: send do NAWS
td: rcv will TSPEED
td: rcv will LFLOW
td: send do LFLOW
td: rcv will LINEMODE
td: send dont LINEMODE
td: rcv will NEW-ENVIRON
td: rcv do STATUS
td: send will STATUS
td: rcv wont XDISPLOC
td: rcv suboption NAWS 0 80 (80) 0 44 (44)
td: rcv suboption TERMINAL-SPEED IS 38400,38400
td: rcv suboption ENVIRON IS
td: rcv suboption TERMINAL-TYPE IS "XTERM"
td: send do ECHO
td: rcv wont ECHO
```

td: send will ECHO

Kernel 2.6.32-41-pve on an x86_64
server login: td: recv do ECHO

and the login session works and you get a normal shell. Without this you get (this is exactly how it appears on the screen with missing characters, no echo and 'stair stepping' lines:

```
$ telnet localhost
Trying 127.0.0.1...
Connected to localhost.
Escape character is '^['.
```

```
Kernel 2.6.32-41-pve on an x86_64
erver login:
Password:
ast login: Thu Nov 12 13:15:58 from test
]0;guest1@server:~[guest1@server ~]$
```

Thanks
