Subject: Re: Enable SSH by default after reboot? Posted by Vasily Tarasov on Thu, 14 Sep 2006 07:15:06 GMT

View Forum Message <> Reply to Message

Quote:So there is no way to reboot the VPS from the Shell inside the VPS without typing restart in the physical node?

You're right... During reboot init of VE is killed and nobody can give birth to new init.

Quote: Are there any control panels that solved this problem?

Sorry, but I don't know any...

There is a solution however. And it even works for some templates!

VE on runlevel 6 (reboot) creates file, that indicates that restart happened. Thus we can create cron job, that will go through all mounted (but not started) VEs and if the "indicator" file exist - start VE.

By default vzctl goes with file /etc/cron.d/vpsreboot that every 5 minutes invokes /usr/share/vzctl/scripts/vpsreboot

For FC4 ob HN and FC4 in VE it works.

Problems persist while different distinbutions/templates are tuned differently:

- 1) Your crond on HN should use /etc/cron.d/vpsreboot.
- 2) Your VE template should create indicator file.

However, these problems can simply be solved by hand.

HTH, vass.