Subject: How to enter a "Not Running Container" Posted by d.har on Sat, 28 Apr 2012 21:08:02 GMT

View Forum Message <> Reply to Message

Hello,

Recently one of our client suffered because his VPS stopped booting. I tried starting it from main node but i get the following.

vzctl start 336

Starting container ...
Container is mounted

Adding IP address(es): XXX.XXX.XXX.XXX

Setting CPU limit: 400 Setting CPU units: 1000

Setting CPUs: 4

Unable to start init, probably incorrect template

Container start failed Stopping container ... Container was stopped Container is unmounted

Both our main node and the container(VPS) is running Centos 5.

I would like to ask the following:

1- Can it be fixed?

If yes, what is the fix? (I have 0 knowledge)

2- If not, then i would like to do the followings

I would like to copy MYSQL DB And the Home directory from the effected container to my main node. And then copy them to another container. (I have 0 knowledge)

Please look at my issue. Thanks

Kind Regards,

Har.

Subject: Re: How to enter a "Not Running Container" Posted by potatosalad on Tue, 01 May 2012 18:45:17 GMT

View Forum Message <> Reply to Message

If you can't get things fixed on the container, you could try the following...

CTID=336
mount proc /vz/private/\$CTID/proc -t proc mount sys /vz/private/\$CTID/sys -t sysfs mount --bind /dev /vz/private/\$CTID/dev

chroot /vz/private/\$CTID

You should be chrooted into the container's root with everything mounted that you would need to start up mysqld manually and dump whatever you need.

Once you're done, just make sure to exit out of the chroot and unmount everything...

umount /vz/private/\$CTID/dev umount /vz/private/\$CTID/sys umount /vz/private/\$CTID/proc

Hope that helps!