
Subject: vzmigrate error

Posted by [Darryl Ross](#) on Sat, 02 Dec 2006 01:18:57 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi All,

I'm having a problem migrating a guest from one machine to another. It's stopping with an error about the second level quotas, which I'm not using.

Is there a way to disable that?

Regards

Darryl

```
[root@noddy vz]# vzmigrate --keep-dst --online -r yes -v 172.16.1.225 241
```

```
OPT:--keep-dst
```

```
OPT:--online
```

```
OPT:-r
```

```
OPT:-v
```

```
OPT:172.16.1.225
```

```
Starting online migration of VE 241 on 172.16.1.225
```

```
OpenVZ is running...
```

```
  Loading /etc/vz/vz.conf and /etc/vz/conf/241.conf files
```

```
  Check IPs on destination node: 172.16.1.241
```

```
Preparing remote node
```

```
  Copying config file
```

```
241.conf
```

```
100% 1816
```

```
1.8KB/s 00:00
```

```
WARNING: Settings were not saved and will be resetted to original values  
on next start (use --save flag)
```

```
  Creating remote VE root dir
```

```
  Creating remote VE private dir
```

```
Initializing remote quota
```

```
  Quota init
```

```
  Turning remote quota on
```

```
Syncing private
```

```
Live migrating VE
```

```
  Suspending VE
```

```
Setting up checkpoint...
```

```
  suspend...
```

```
  get context...
```

```
Checkpointing completed succesfully
```

```
  Dumping VE
```

```
Setting up checkpoint...
```

```
  join context..
```

```
  dump...
```

Checkpointing completed succesfully

Copying dumpfile
dump.241

100% 5212KB

5.1MB/s 00:00

Syncing private (2nd pass)

Syncing 2nd level quota

Dumping 2nd level quota

vzquota : (error) Can't open quota file for id 241, maybe you need to
reinitialize quota: No such file or directory

Failed to dump 2nd level quota

Resuming...

vzquota : (error) Quota is not running for id 241

Subject: Re: vzmigrate error

Posted by [Vasily Tarasov](#) on Mon, 04 Dec 2006 08:58:26 GMT

[View Forum Message](#) <> [Reply to Message](#)

This is easy to disable 2nd level quota: just remove line with
QUTAUGIDLIMIT for /etc/vz.conf and /etc/conf/<veid>.conf and restart VE.
You should do it on both nodes: source and destination.

HTH,
Vasily.

Darryl Ross wrote:

> Hi All,
>
> I'm having a problem migrating a guest from one machine to another. It's
> stopping with an error about the second level quotas, which I'm not using.
>
> Is there a way to disable that?
>
> Regards
> Darryl
