Subject: how to set subnet mask Posted by kasarfa on Tue, 05 Dec 2006 15:33:49 GMT

View Forum Message <> Reply to Message

Im tyring to setup VPS with OpenVZ.

I used vzctl command. vzctl set 101 --ipadd [IP]

and checked conf cat /etc/sysconfig/vz-scripts/101.conf IP\_ADDRESS="[IP]"

After that, Start OpenVZ and enter. But, Can not connect network. Because, VE's subnet mask is not HW's.

HW's subnet mask 255.255.255.248 VE's subnet mask 255.255.255.255

I tried to change subnet mask and restart network.

vi /etc/sysconfig/network-scripts/ifcfg-venet0:0 NETMASK=255.255.255.248 #NETMASK=255.255.255.255

/etc/init.d/network restart

VE's success to connect HW. But, after restart OpenVZ, subnet mask back to 255.255.255.255

Anyone know set subnet mask? I could not find command in vzctl --help.

Subject: Re: how to set subnet mask
Posted by Vasily Tarasov on Wed, 06 Dec 2006 07:58:36 GMT
View Forum Message <> Reply to Message

Hello,

I really don't know why do you need it ('cause <venet0 in VE> is directly connected to <venet on HN>), but will explain how to do it.

Step by step guide (works at least for vzctl-3.0.13):

1. Determine which template do you use for the VE in question:

```
# grep TEMPL /etc/vz/conf/202.conf
OSTEMPLATE="fedora-core-4-i386-default
#
```

So this is fedora-core-4 in my case.

2. Figure out which script runs to setup network for this template:

```
# grep = /etc/vz/dists/fedora-core-4.conf
ADD_IP=redhat-add_ip.sh
DEL_IP=redhat-del_ip.sh
SET_HOSTNAME=redhat-set_hostname.sh
SET_DNS=set_dns.sh
SET_USERPASS=set_userpass.sh
SET_UGID_QUOTA=set_ugid_quota.sh
POST_CREATE=postcreate.sh
#
```

I can see that script redhat-add\_ip.sh runs when we do --ipadd.

4. Modify script in order it to use required NETMASK:

# grep NETMASK /etc/vz/dists/scripts/redhat-add\_ip.sh

NETMASK=255.255.255.255

NETMASK=255.255.255.255" > \${IFCFG\_DIR}/bak/\${VENET\_DEV\_CFG}:\${ifnum} || \

# vim /etc/vz/dists/scripts/redhat-add ip.sh

[root@white ~]# grep NETMASK /etc/vz/dists/scripts/redhat-add ip.sh

NETMASK=255.255.255.248

NETMASK=255.255.255.248" > \${IFCFG\_DIR}/bak/\${VENET\_DEV\_CFG}:\${ifnum} || \

Check that it works:

# vzctl start 202
Starting VE ...
VE is mounted
Setting CPU units: 1000
VE start in progress...
# vzctl enter 202
entered into VE 202
[ve]# ifconfig | grep Mask

inet addr:127.0.0.1 Mask:255.0.0.0

inet addr:127.0.0.1 P-t-P:127.0.0.1 Bcast:0.0.0.0 Mask:255.255.255.248

[ve]# exit logout

exited from VE 202

# vzctl stop 202
Stopping VE ...
VE was stopped
VE is unmounted
# /etc/init.d/vz stop
Stopping OpenVZ: [ OK ]
# /etc/init.d/vz start
Starting OpenVZ: [ OK ]
Bringing up interface venet0: [ OK ]
Configuring interface venet0: [ OK ]

# vzctl start 202 Starting VE ... VE is mounted

Setting CPU units: 1000 VE start in progress... # vzctl enter 202 entered into VE 202

[VE]# ifconfig -a | grep Mask

inet addr:127.0.0.1 Mask:255.0.0.0

inet addr:127.0.0.1 P-t-P:127.0.0.1 Bcast:0.0.0.0 Mask:255.255.255.248

HTH, Vasily.