
Subject: Vzsplit question

Posted by [Romeo Theriault](#) on Tue, 12 Dec 2006 01:00:56 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hello, I think I'm not entirely understanding how vzsplit works.

I want to split my server up into 20 ve's. So I ran this:

```
vzsplit -n 20 -f vps.mytest
```

Which creates the appropriate file. Which I use as my template when creating new VE's. Great.

But when I run vzcalc on one of the ve's that I've created with the template made with vzsplit, this is what it shows:

```
[root@vz ~]# vzcalc 101
Resource   Current(%) Promised(%) Max(%)
Memory     0.28      20.45      22.46
```

I'm confused because I thought splitting it up for 20 ve's would give a promised of around 5%, not 20%. How can 20 ve's each be promised 20%?

Here is the output of vzcpucheck with two ve's running with the aforementioned template from above.

```
[root@vz ~]# vzcpucheck
Current CPU utilization: 35758
Power of the node: 183537
```

Here is the vz script called 101.conf that the above vzsplit created. I modified only the Disk quota's and the hostname, ip_address, nameservers paramters:

```
NUMPROC="400:400"
AVNUMPROC="111:111"
NUMTCPSOCK="400:400"
NUMOTHERSOCK="400:400"
VMGUARPAGES="310531:2147483647"
```

```
# Secondary parameters
KMEMSIZE="9130147:10043161"
TCPSNDBUF="1404982:3043382"
TCPRCVBUF="1404982:3043382"
OTHERSOCKBUF="702491:2340891"
DGRAMRCVBUF="702491:702491"
```

```
OOMGUARPAGES="310531:2147483647"  
PRIVVMPAGES="310531:341584"
```

```
# Auxiliary parameters
```

```
LOCKEDPAGES="445:445"  
SHMPAGES="31053:31053"  
PHYSPAGES="0:2147483647"  
NUMFILE="3552:3552"  
NUMFLOCK="355:390"  
NUMPTY="40:40"  
NUMSIGINFO="1024:1024"  
DCACHESIZE="1986361:2045952"  
NUMIPTENT="100:100"
```

```
# Disk space
```

```
DISKSPACE="5000000:5100000"  
DISKINODES="665374:731912"  
QUOTATIME="600"
```

```
# CPU Scheduling
```

```
CPUUNITS="8573"  
VE_ROOT="/vz/root/$VEID"  
VE_PRIVATE="/vz/private/$VEID"  
OSTEMPLATE="centos-4-i386-default"  
ORIGIN_SAMPLE="vps.mytest"  
ONBOOT="yes"  
HOSTNAME="not.a.real.hostname.com"  
IP_ADDRESS="555.555.555.555"  
NAMESERVER="555.555.555.555"
```

The script also validates with vzcfgvalidate, so I'm assuming this is an error of my understanding. Would someone be kind enough to explain to me how this works.

Thanks,

Romeo

Subject: Re: Vzsplit question

Posted by [TheWiseOne](#) on Tue, 12 Dec 2006 01:04:53 GMT

[View Forum Message](#) <> [Reply to Message](#)

Romeo Theriault wrote:

> Hello, I think I'm not entirely understanding how vzsplit works.

>

> I want to split my server up into 20 ve's. So I ran this:

>
> vzsplrit -n 20 -f vps.mytest
>
> Which creates the appropriate file. Which I use as my template when creating
> new VE's. Great.
>
> But when I run vzcalc on one of the ve's that I've created with the template
> made with vzsplrit, this is what it shows:
>
> [root@vz ~]# vzcalc 101
> Resource Current(%) Promised(%) Max(%)
> Memory 0.28 20.45 22.46
>

Try vzsplrit with "-s 0", the regular way it takes swap into account
which is generally a bad idea.

Regards,
Matt

Subject: Re: Vzsplrit question
Posted by [Romeo Theriault](#) on Tue, 12 Dec 2006 20:55:38 GMT
[View Forum Message](#) <> [Reply to Message](#)

On 12/11/06 8:04 PM, "Matt Ayres" <matta@tektonic.net> wrote:

>
>
> Romeo Theriault wrote:
>> Hello, I think I'm not entirely understanding how vzsplrit works.
>>
>> I want to split my server up into 20 ve's. So I ran this:
>>
>> vzsplrit -n 20 -f vps.mytest
>>
>> Which creates the appropriate file. Which I use as my template when creating
>> new VE's. Great.
>>
>> But when I run vzcalc on one of the ve's that I've created with the template
>> made with vzsplrit, this is what it shows:
>>
>> [root@vz ~]# vzcalc 101
>> Resource Current(%) Promised(%) Max(%)
>> Memory 0.28 20.45 22.46
>>
>
> Try vzsplrit with "-s 0", the regular way it takes swap into account

> which is generally a bad idea.

>

> Regards,

> Matt

Thank you! Using the -s 0 gives results much more like I was expecting.

Romeo
