

---

Subject: \*SOLVED\* Fedora core 6 and permission  
Posted by [santa](#) on Wed, 17 Jan 2007 07:44:07 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

FC6, 2.6.18-ovz028test010.1-smp

```
On HN and on all VPS
[root@ua3 test]# umask
0022
[root@ua3 test]# mkdir 1
[root@ua3 test]# ls -al
```

```
[root@ua3 test]# umask 777
[root@ua3 test]# umask
0777
[root@ua3 test]# mkdir 2
[root@ua3 test]# ls -al
```

```
[root@ua3 test]# touch 3
[root@ua3 test]# ls -al
```

```
[root@ua3 test]# umask 000
[root@ua3 test]# umask
0000
[root@ua3 test]# touch 5
[root@ua3 test]# ls -al
```

I tried 2.6.18-ovz028test010.1-smp (rpm and src.rpm),  
2.6.18-ovz028test007.1-smp.

I am not trying 2.6.9 kernel because it conflicts with others rpms.  
If i booting with non vz kernel 2.6.18-1.2869.fc6, there is no problem with permission.

---

---

Subject: Re: Fedora core 6 and permission  
Posted by [dev](#) on Tue, 30 Jan 2007 13:47:04 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

it's kernel bug when ACL support is off and filesystem is mounted with acl option.  
you can remount fs without ACL. will be fixed in next kernel also.  
or you can enable CONFIG\*\_ACL options in your .config file yourself.

---