
Subject: openvz not working - Unable to open /dev/vzctl

Posted by [Rick C](#) **on** Mon, 20 Aug 2007 16:50:23 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi there,

I am running openvz with hypervm and it was working fine, but now none of my vm's are not working i can not access them, when i go to thier ip address's i just get the servers root apache page.

I tried to start the vms via hypervm control panel but i get this error?

Failed to get Status from localhost. Server said:

no_kernel_support_for_openvz_check_if_right_kernel

()

i have checked /etc/grub.conf and its set to default=0

also if i try to connect to the server via command access in hyper vm i get this error!

Unable to open /dev/vzctl: No such file or directory

Please check that vzdev kernel module is loaded and you have sufficient permissions to access the file.

I recon its a problem with openvz

any ideas please? It was fully working, i had 2 vps servers running one with cpanel and had sites resloved to it and another with centos base install on it? all working perfect.

kind regards,

Rick

Subject: Re: openvz not working - Unable to open /dev/vzctl

Posted by [locutius](#) **on** Mon, 20 Aug 2007 16:59:04 GMT

[View Forum Message](#) <> [Reply to Message](#)

uname -a

will tell you what kernel you have loaded

Subject: Re: openvz not working - Unable to open /dev/vzctl

Posted by [Rick C](#) **on** Mon, 20 Aug 2007 17:02:05 GMT

[View Forum Message](#) <> [Reply to Message](#)

2.6.18-8.1.8.el5 #1 SMP Tue Jul 10 06:50:22 EDT 2
GNU/Linux

007 i686 i686 i386

what do you make of it? is it the right one?
thanks for your reply

Subject: Re: openvz not working - Unable to open /dev/vzctl

Posted by [locutius](#) on Mon, 20 Aug 2007 17:13:57 GMT

[View Forum Message](#) <> [Reply to Message](#)

that is not an OpenVZ kernel. a VZ kernel will look like something like this (the latest):

2.6.18-8.1.8.el5.028stab039.1PAE

you are looking for the .028stab039.1PAE signifying the VZ kernel. edit your grub file and comment out all the other kernels with a #

but before you do that consider first what might have happened to cause your situation

Subject: Re: openvz not working - Unable to open /dev/vzctl

Posted by [Rick C](#) on Mon, 20 Aug 2007 17:19:28 GMT

[View Forum Message](#) <> [Reply to Message](#)

grub.conf looks like this

```
#boot=/dev/sda
default=0
timeout=5
splashimage=(hd0,0)/grub/splash.xpm.gz
hiddenmenu
title CentOS (2.6.18-8.1.8.el5)
    root (hd0,0)
    kernel /vmlinuz-2.6.18-8.1.8.el5 ro root=LABEL=/
    initrd /initrd-2.6.18-8.1.8.el5.img
title CentOS (2.6.18-8.1.8.el5.028stab039.1)
    root (hd0,0)
    kernel /vmlinuz-2.6.18-8.1.8.el5.028stab039.1 ro root=LABEL=/
    initrd /initrd-2.6.18-8.1.8.el5.028stab039.1.img
title CentOS (2.6.18-8.el5)
    root (hd0,0)
    kernel /vmlinuz-2.6.18-8.el5 ro root=LABEL=/
    initrd /initrd-2.6.18-8.el5.img
```

so needs to be

```
#boot=/dev/sda
default=0
timeout=5
splashimage=(hd0,0)/grub/splash.xpm.gz
hiddenmenu
#title CentOS (2.6.18-8.1.8.el5)
    root (hd0,0)
```

```
kernel /vmlinuz-2.6.18-8.1.8.el5 ro root=LABEL=/  
initrd /initrd-2.6.18-8.1.8.el5.img  
title CentOS (2.6.18-8.1.8.el5.028stab039.1)  
root (hd0,0)  
kernel /vmlinuz-2.6.18-8.1.8.el5.028stab039.1 ro root=LABEL=/  
initrd /initrd-2.6.18-8.1.8.el5.028stab039.1.img  
#title CentOS (2.6.18-8.el5)  
root (hd0,0)  
kernel /vmlinuz-2.6.18-8.el5 ro root=LABEL=/  
initrd /initrd-2.6.18-8.el5.img
```

is that right? sorry am new to Vz

Subject: Re: openvz not working - Unable to open /dev/vzctl
Posted by [locutius](#) on Mon, 20 Aug 2007 17:24:28 GMT

[View Forum Message](#) <> [Reply to Message](#)

edit your grub to look like this:

```
#boot=/dev/sda  
default=1  
timeout=5  
#splashimage=(hd0,0)/grub/splash.xpm.gz  
#hiddenmenu  
#title CentOS (2.6.18-8.1.8.el5)  
#root (hd0,0)  
#kernel /vmlinuz-2.6.18-8.1.8.el5 ro root=LABEL=/  
#initrd /initrd-2.6.18-8.1.8.el5.img  
title OpenVZ CentOS (2.6.18-8.1.8.el5.028stab039.1)  
root (hd0,0)  
kernel /vmlinuz-2.6.18-8.1.8.el5.028stab039.1 ro root=LABEL=/  
initrd /initrd-2.6.18-8.1.8.el5.028stab039.1.img  
#title CentOS (2.6.18-8.el5)  
#root (hd0,0)  
#kernel /vmlinuz-2.6.18-8.el5 ro root=LABEL=/  
#initrd /initrd-2.6.18-8.el5.img
```

notice i also changed the title of the kernel adding "OpenVZ"

remember to leave 1 x blank line at the end of the file

Subject: Re: openvz not working - Unable to open /dev/vzctl
Posted by [Rick C](#) on Mon, 20 Aug 2007 19:59:59 GMT

[View Forum Message](#) <> [Reply to Message](#)

excellent thanks that worked, need to figure out now why i cant get to the vps servers!

Subject: Re: openvz not working - Unable to open /dev/vzctl

Posted by [locutius](#) on Mon, 20 Aug 2007 20:12:31 GMT

[View Forum Message](#) <> [Reply to Message](#)

vzlist -a

are they started?

Subject: Re: openvz not working - Unable to open /dev/vzctl

Posted by [Rick C](#) on Mon, 20 Aug 2007 20:24:03 GMT

[View Forum Message](#) <> [Reply to Message](#)

yes says they are running, but cant get to cpanel on one that was running and when you ssh to them you get the root server by the ip?

thanks for the help

Subject: Re: openvz not working - Unable to open /dev/vzctl

Posted by [Rick C](#) on Mon, 20 Aug 2007 21:55:07 GMT

[View Forum Message](#) <> [Reply to Message](#)

deleted vms and recreated all ok, thanks for your help

Subject: Re: openvz not working - Unable to open /dev/vzctl

Posted by [formatyk](#) on Fri, 22 Jun 2012 19:12:22 GMT

[View Forum Message](#) <> [Reply to Message](#)

This is my grub configuration

does not work

Please help

default=1

timeout=5

title OpenVZ CentOS (2.6.18-308.el5.028stab099.3)
kernel /boot/vmlinuz-2.6.18-308.el5.028stab099.3 root=/dev/sda1 ro sysfs.deprecated=1
selinux=0
root (hd0,0)
initrd /boot/initrd-2.6.18-308.el5.028stab099.3.img

```
#title OpenVZ (2.6.18-274.18.1.el5.028stab098.1)
#kernel /boot/vmlinuz-2.6.18-274.18.1.el5.028stab098.1 root=/dev/sda1 ro
sysfs.deprecated=1 selinux=0
#root (hd0,0)
#initrd /boot/initrd-2.6.18-274.18.1.el5.028stab098.1.img
#title OpenVZ (2.6.18-274.7.1.el5.028stab095.1)
#kernel /boot/vmlinuz-2.6.18-274.7.1.el5.028stab095.1 root=/dev/sda1 ro
sysfs.deprecated=1 selinux=0
#root (hd0,0)
#initrd /boot/initrd-2.6.18-274.7.1.el5.028stab095.1.img
#title OpenVZ (2.6.18-274.3.1.el5.028stab094.3)
#kernel /boot/vmlinuz-2.6.18-274.3.1.el5.028stab094.3 root=/dev/sda1 ro
sysfs.deprecated=1 selinux=0
#root (hd0,0)
#initrd /boot/initrd-2.6.18-274.3.1.el5.028stab094.3.img
#title CentOS (2.6.32-042stab039.2)
#kernel /boot/vmlinuz-2.6.32-042stab039.2 root=/dev/sda1 ro sysfs.deprecated=1
#root (hd0,0)
#initrd /boot/initrd-2.6.32-042stab039.2.img
#title linux centos5_64
#kernel /boot/bzImage-2.6.38.2-xxxx-grs-ipv6-64 root=/dev/sda1 ro
#root (hd0,0)
```

Subject: Re: openvz not working - Unable to open /dev/vzctl
Posted by [Ales](#) on Sat, 23 Jun 2012 03:28:55 GMT

[View Forum Message](#) <> [Reply to Message](#)

Should be default=0 not default=1.

Subject: Re: openvz not working - Unable to open /dev/vzctl
Posted by [formatyk](#) on Sat, 23 Jun 2012 04:00:17 GMT

[View Forum Message](#) <> [Reply to Message](#)

not working .

default=0
timeout=1

```
title OpenVZ (2.6.18-308.el5.028stab099.3)
root (hd0,0)
kernel /boot/vmlinuz-2.6.18-308.el5.028stab099.3 root=/dev/sda1
initrd /boot/initrd-2.6.18-308.el5.028stab099.3.img
```

```
#title OpenVZ (2.6.18-274.18.1.el5.028stab098.1)
#kernel /boot/vmlinuz-2.6.18-274.18.1.el5.028stab098.1 root=/dev/sda1 ro
sysfs.deprecated=1 selinux=0
#root (hd0,0)
#initrd /boot/initrd-2.6.18-274.18.1.el5.028stab098.1.img
#title OpenVZ (2.6.18-274.7.1.el5.028stab095.1)
#kernel /boot/vmlinuz-2.6.18-274.7.1.el5.028stab095.1 root=/dev/sda1 ro
sysfs.deprecated=1 selinux=0
#root (hd0,0)
#initrd /boot/initrd-2.6.18-274.7.1.el5.028stab095.1.img
#title OpenVZ (2.6.18-274.3.1.el5.028stab094.3)
#kernel /boot/vmlinuz-2.6.18-274.3.1.el5.028stab094.3 root=/dev/sda1 ro
sysfs.deprecated=1 selinux=0
#root (hd0,0)
#initrd /boot/initrd-2.6.18-274.3.1.el5.028stab094.3.img
#title CentOS (2.6.32-042stab039.2)
#kernel /boot/vmlinuz-2.6.32-042stab039.2 root=/dev/sda1 ro sysfs.deprecated=1
#root (hd0,0)
#initrd /boot/initrd-2.6.32-042stab039.2.img
#title linux centos5_64
#kernel /boot/bzImage-2.6.38.2-xxxx-grs-ipv6-64 root=/dev/sda1 ro
#root (hd0,0)
```
