

---

Subject: \*SOLVED\* ssh connection problem in guest OS

Posted by [gogisnim](#) on Sun, 26 Aug 2007 13:36:22 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hi, everyone ~

In guest OS, I can't connect ssh.

```
host ip - 1.1.1.200
guest ip - 1.1.2.200
```

```
host # vzctl create 2200 --ostemplate gentoo-2.6.18
host # vzctl set 2200 --save --onboot=yes --ipadd 1.1.2.200 --nameserver 1.1.1.200 --nameserver
168.126.63.1 --hostname guest --diskspace 700000:750000 --userpasswd test:1111
host # vzctl start 2200 && vzctl enter 2200
```

```
guest # ssh root@1.1.1.200
PRNG is not seeded
guest #
```

I read /dev/random create.

```
host # vzctl exec 2200 mknod /dev/random c 1 8
```

```
guest # ssh root@1.1.1.200
Host key verification failed.
```

I tried to connect into local sshd of guest.

```
guest # /etc/init.d/sshd start
* Generating RSA-Hostkey...
PRNG is not seeded
```

This is my system info.

```
host # cat /etc/vz/conf/2200.conf
ONBOOT="yes"
```

```
AVNUMPROC="40:40"
NUMPROC="65:65"
NUMTCPSOCK="80:80"
```

NUMOTHERSOCK="80:80"  
VMGUARPAGES="6144:2147483647"

KMEMSIZE="2752512:2936012"  
TCPSNDBUF="319488:524288"  
TCPRCVBUF="319488:524288"  
OTHERSOCKBUF="132096:336896"  
DGRAMRCVBUF="132096:132096"  
OOMGUARPAGES="6144:2147483647"

LOCKEDPAGES="32:32"  
SHMPAGES="8192:8192"  
PRIVVMPAGES="49152:53575"  
NUMFILE="2048:2048"  
NUMFLOCK="100:110"  
NUMPTY="16:16"  
NUMSIGINFO="256:256"  
DCACHESIZE="1048576:1097728"  
PHYSPAGES="0:2147483647"  
NUMIPTENT="128:128"

DISKSPACE="700000:750000"  
DISKINODES="200000:220000"  
QUOTATIME="0"

CPUUNITS="1000"  
VE\_ROOT="/vz/root/\$VEID"  
VE\_PRIVATE="/vz/private/\$VEID"  
OSTEMPLATE="gentoo-2.6.18"  
ORIGIN\_SAMPLE="vps.basic"  
IP\_ADDRESS="1.1.2.200"  
HOSTNAME="guest"  
NAMESERVER="1.1.2.200 168.126.63.1"

```
guest # df -h
Filesystem      Size  Used Avail Use% Mounted on
simfs           684M 452M 233M  67% /
tmpfs           220M   76K 220M   1% /dev
tmpfs           220M    0 220M   0% /dev/shm
```

```
guest # mount
simfs on / type simfs (rw)
proc on /proc type proc (rw,nosuid,nodev,noexec)
sysfs on /sys type sysfs (rw,nosuid,nodev,noexec)
tmpfs on /dev type tmpfs (rw,nosuid)
devpts on /dev/pts type devpts (rw,nosuid,noexec)
```

tmpfs on /dev/shm type tmpfs (rw,nosuid,nodev,noexec)

Thank you

---

---

Subject: Re: ssh connection problem in guest OS  
Posted by [kir](#) on Sun, 26 Aug 2007 14:08:09 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

That's bad that /dev is mounted using tmpfs. This is good for the host system and if you use udev, but for VE a much saner way would be to disable mounting /dev using tmpfs, disable udevd and then create all the devices you need in VE.

After that, install strace into a VE and run sshd under strace to see what the problem is.

---

---

Subject: Re: ssh connection problem in guest OS  
Posted by [gogisnim](#) on Sun, 26 Aug 2007 21:59:05 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

I solved it.

First of all, how to create gentoo base VE template was fatal !!

[http://wiki.openvz.org/Gentoo\\_template\\_creation](http://wiki.openvz.org/Gentoo_template_creation)

I created the template except "Edit /etc/init.d/checkroot", "Edit /sbin/rc" and "Set up udev" in this url.

I deleted old template and created new template step by step.

Now, I can connect ssh into host.

```
guest # df -h
Filesystem      Size  Used Avail Use% Mounted on
simfs           1.0G  410M  615M  41% /
```

```
guest # mount
simfs on / type simfs (rw)
proc on /proc type proc (rw,nosuid,nodev,noexec)
devpts on /dev/pts type devpts (rw,nosuid,noexec)
```

```
guest # ssh root@host
Password:
```

host #

To understand tmpfs is difficult until now, but I learn.

Thank you very much indeed.  
I'm tired..

---