## Subject: veth: No Connection between host and guest Posted by Barzille on Thu, 30 Aug 2007 13:21:08 GMT

View Forum Message <> Reply to Message

Hello there.

I am comparing different vm solutions for performance and security aspects and now I want to try out openVZ.

My system is the following:

Ubuntu 7.04 as Host with 2.6.18-028stab035.1-ovz-smp kernel. I installed ubuntu-6.06-i386-minimal template as guest.

Because I want to have an IP Adress for each VE in my LAN and internet access I decided to use veth devices. I performed the following steps mentioned in the wiki:

- 1. vzctl create 101 --ostemplate ubuntu....
- 2. vzctl set 101 --hostname guest1 --save
- 3. vzctl set 101 --netif\_add eth0,onerandommacaddress,veth101.0,anotherrandommacaddress --save
- 4. After that I used the script for persistent veth connection and added those two lines in my config file. VETH IP ADDRESS = 192.168.160.94 and CONFIG CUSTOMIZED="yes"
- 5. In my host system and in the guest are forwarding, proxy\_arp and ip\_forward enabled for veth101.0 (host) and eth0 (guest)
- 6. (quest) /etc/resolve.conf has the same entries as in the file at host
- 7. I added a default route in guestsystem: /sbin/ip route add default dev eth0
- 8. and now, there's no connection via ping neither to the host, nor to the internet and vice versa

Any hints?

Thank you

Subject: Re: veth: No Connection between host and guest Posted by khorenko on Thu, 30 Aug 2007 14:58:34 GMT

View Forum Message <> Reply to Message

Hello,

1) venet is quite suitable to the configuration you described: an IP Adress for each VE in my LAN and internet access, and in this case you don't have to write additional scripts/customize configs. So venet configuration is much less error prone.

Might be it makes sense to try venet approach?

2) if you still want to use veth, could you please first try to do all the staff manually without making the configuration persistent. In this case you can post the exact commands you typed and we might see something wrong. Please, post here exact commands you do and their outputs. Thank you.

P.S. also `ip a I` and `ip r I` outputs both in the HN and the VE are appreciated (after the configuration completed).

Subject: Re: veth: No Connection between host and guest Posted by Barzille on Thu, 30 Aug 2007 15:10:41 GMT

View Forum Message <> Reply to Message

Hi,

is it possible to give my ve's ipaddresses with venet, so that they can be used as static machines? For example as Webserver, as Mailserver, as ...? If the answer is yes, then it will do it for my purpose.

I also tried it with venet. I achieved connections between host and guest, but no connection between guest and other clients in my lan and none to internet. Because of this, I tried veth...

If venet is enough, I will give it a try tomorrow at work!

Maik

Subject: Re: veth: No Connection between host and guest Posted by khorenko on Fri, 31 Aug 2007 06:55:28 GMT

View Forum Message <> Reply to Message

Barzille wrote on Thu, 30 August 2007 19:10Hi,

is it possible to give my ve's ipaddresses with venet, so that they can be used as static machines? For example as Webserver, as Mailserver, as ...? If the answer is yes, then it will do it for my purpose.

Yes, using venet you can assign IPs to VEs and use them as you asked.

(just for clarification - if you are going to make VEs accessible from the internet you have to assign them public IPs like to any standalone node or have the deal with source based routing/NAT/etc.) How to add an IP to venet device: http://wiki.openvz.org/Venet

Differences between veth and venet: http://wiki.openvz.org/Differences between venet and veth

Also please check your sysctl configuration, this might be the reason of your network failures (especially 'ip\_forward' sysctl): http://wiki.openvz.org/Quick\_installation#sysctl

Hope this helps.

--

Konstantin.

Subject: Re: veth: No Connection between host and guest

## Posted by Barzille on Fri, 31 Aug 2007 09:13:41 GMT

View Forum Message <> Reply to Message

Ok,

I got it working. One of the problems was /proc/sys/net/ipv4/conf/venet0/proxy\_arp because it is set to 0 (in ve) after each restart of the ve... Is there a possibility to make it default to 1?

Subject: Re: veth: No Connection between host and guest Posted by khorenko on Fri, 31 Aug 2007 09:36:15 GMT

View Forum Message <> Reply to Message

[HN]# ip a l

. . .

1: venet0: <BROADCAST,POINTOPOINT,NOARP,UP> mtu 1500 qdisc noqueue link/void

. .

Well, you see venet is not an ethernet device, and in particular it doesn't allow arp packets to go through it (NOARP flag), so it's ok to stay venet0.proxy\_arp 0, this shouldn't influence on the system in any case.

Subject: Re: veth: No Connection between host and guest Posted by Barzille on Fri, 31 Aug 2007 12:34:53 GMT

View Forum Message <> Reply to Message

finist wrote on Fri, 31 August 2007 05:36[HN]# ip a I

. . .

, so it's ok to stay venet0.proxy\_arp 0, this shouldn't influence on the system in any case.

But with 0 it's not working, it has to be 1 in order to have network access. But my question is how to make it 1 by default at every start up of the virtual machine?

Subject: Re: veth: No Connection between host and guest Posted by khorenko on Fri, 31 Aug 2007 13:37:51 GMT

View Forum Message <> Reply to Message

Barzille wrote on Fri, 31 August 2007 16:34But with 0 it's not working, it has to be 1 in order to have network access.

It's very strange and i'd be appreciated if you post here the command (with the output) which doesn't work with proxy\_arp on venet0 disabled and works if proxy\_arp is "enabled".

Quote:But my question is how to make it 1 by default at every start up of the virtual machine?

For example you can put echo 1 > /proc/sys/net/ipv4/conf/venet0/proxy\_arp

to the /etc/rc.d/rc.local script inside a VE.

Subject: Re: veth: No Connection between host and guest Posted by Barzille on Fri, 31 Aug 2007 13:44:02 GMT

View Forum Message <> Reply to Message

Ok, I will do so on monday when I am back at work, so long, thank you