

---

Subject: Disk quota on gentoo template

Posted by [steffen.zieger](#) on Wed, 01 Mar 2006 22:14:37 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hello,

I've got a problem with my gentoo-vps.

I'm using the same configuration file for a gentoo and a debian vps.

I've a limit on disk space set to about 5GB. On debian-vps this limit works and I can use all of the 5Gb.

On Gentoo-vps I can only use about 1,2Gb.

Does anybody got an idea, where the problem is?

TIA,  
Steffen

---

---

Subject: Re: Disk quota on gentoo template

Posted by [kir](#) on Wed, 01 Mar 2006 22:32:30 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Can you post some numbers to illustrate your findings? I.e. cat /proc/vz/vzquota, df, du -sh / in VPS etc. etc.

---

---

Subject: Re: Disk quota on gentoo template

Posted by [steffen.zieger](#) on Thu, 02 Mar 2006 07:56:44 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hello,

sure. Here we go.

df in gentoo-vps:

Filesystem	1K-blocks	Used	Available	Use%	Mounted on
simfs	5000000	965040	4034960	20%	/

du -sh /:

```
pegasus / # du -sh /
929M /
```

Ok, I've found the problem.

cat /proc/vz/quota:

qid: path	usage	softlimit	hardlimit	time	expire
100: /vz/private/100					
1k-blocks	1124974	5000000	5120000	0	0
inodes	200001	200000	220000	1141285151	0
111: /vz/private/111					
1k-blocks	1662919	5000000	5100000	0	0
inodes	85754	200000	220000	0	0

Both are running into the same problem. On debian-vps (111) there are only more inodes unused than on gentoo-vps (100).

But one problem is left:

There is a softlimit and a hardlimit. Hardlimit is 20000 inodes bigger than softlimit, but if I'm reaching the softlimit, a message is printed, that disk quota is exceeded. Why?

What is a sane number for inodes if I want to have 5Gb?

TIA,  
Steffen

---

---

Subject: Re: Disk quota on gentoo template  
Posted by [carlos](#) on Tue, 02 May 2006 13:38:55 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

I have too problem with my gentoo-vps  
I cant install apache. I use emerge apache and I see "disk quota exceeded"

```
my df /
Filesystem      1K-blocks    Used Available Use% Mounted on
-                5000000 1174760 3825240 24% /
```

```
du -sh /
1.2
```

---

---

Subject: Re: Disk quota on gentoo template  
Posted by [kir](#) on Tue, 02 May 2006 13:48:40 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

It looks like you have exceeded your inodes limits. Use `df -i` to check, `vzctl set VEID --diskinodes` to increase.

---

---

Subject: Re: Disk quota on gentoo template  
Posted by [carlos](#) on Tue, 02 May 2006 14:05:32 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

```
df -i /  
Filesystem      Inodes  IUsed  IFree IUse% Mounted on  
-               200000 200000   0 100% /
```

vzctl and VEID command not found

How I can change df -i / to more?

---

---

Subject: Re: Disk quota on gentoo template  
Posted by [kir](#) on Tue, 02 May 2006 14:10:37 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

As I just said:  
vzctl set VEID --diskinodes 400000:450000 --save

---

---

Subject: Re: Disk quota on gentoo template  
Posted by [carlos](#) on Tue, 02 May 2006 14:13:00 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

If I use this I see: command not found

---

---

Subject: Re: Disk quota on gentoo template  
Posted by [kir](#) on Tue, 02 May 2006 14:18:02 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

You can not increase the per-VE limit from inside a VE for obvious reasons. You should use vzctl set from the host system. If you just have a VE and do not have access to the host system, plz ask you sysadmin to raise the diskinodes limit for your VE

---