

---

Subject: Howto config ve of ram 1GB  
Posted by [powervps](#) on Fri, 07 Dec 2007 07:07:24 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Howto config ve of ram 1GB and 1500 Mb and 512 ram

Quote:ONBOOT="yes"

```
# UBC parameters (in form of barrier:limit)
AVNUMPROC="360"
NUMPROC="480"
NUMTCPSOCK="720"
NUMOTHERSOCK="720:720"
VMGUARPAGES="67584:2147483647"
# Secondary parameters
KMEMSIZE="22111846:22754099"
TCPSNDBUF="319488:524288"
TCPRCVBUF="3440640:5406720"
OTHERSOCKBUF="2252160:4194304"
DGRAMRCVBUF="524288:524288"
OOMGUARPAGES="52224:2147483647"
# Auxiliary parameters
LOCKEDPAGES="512:512"
SHMPAGES="43008"
PRIVVMPAGES="131072:139264"
NUMFILE="18624"
NUMFLOCK="376:412"
NUMPTY="32:32"
NUMSIGINFO="512:512"
DCACHESIZE="6819840:7249920"

PHYSPAGES="0:2147483647"
NUMIPTENT="256:256"

# Disk quota parameters (in form of softlimit:hardlimit)
DISKSPACE="104857600:104857600"
DISKINODES="2000000:2200000"
QUOTATIME="0"

# CPU fair sheduler parameter
CPUUNITS="1000"
```

---

Subject: Re: Howto config ve of ram 1GB  
Posted by [powervps](#) on Fri, 07 Dec 2007 07:10:39 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

1GB RAM and 2GB swap

512 RAM and 1GB swap  
256 RAM and 512 Swap  
2000 Ram and 2500 swap

Thx yoy

---

Subject: Re: Howto config ve of ram 1GB  
Posted by [powervps](#) on Fri, 07 Dec 2007 20:11:11 GMT  
[View Forum Message](#) <> [Reply to Message](#)

up

---

Subject: Re: Howto config ve of ram 1GB  
Posted by [blunt](#) on Fri, 07 Dec 2007 21:37:26 GMT  
[View Forum Message](#) <> [Reply to Message](#)

there is no way of saying that you want X of Ram and Y of Swap. You say you want Z of virtual memory and openvz will manage it between ram and swap...

hope this clarifies things up for you

---

Subject: Re: Howto config ve of ram 1GB  
Posted by [powervps](#) on Fri, 07 Dec 2007 22:39:02 GMT  
[View Forum Message](#) <> [Reply to Message](#)

Ok how ican do that any file need to changed  
i have install at my server swap 30 g and real ram 16 g

how ican config them

---

Subject: Re: Howto config ve of ram 1GB  
Posted by [blunt](#) on Fri, 07 Dec 2007 22:59:59 GMT  
[View Forum Message](#) <> [Reply to Message](#)

VMGUARPAGES="32768:2147483647" // 128MB Guaranteed  
VMGUARPAGES="65536:2147483647" // 256MB Guaranteed  
VMGUARPAGES="131072:2147483647" // 512MB Guaranteed

PRIVVMPAGES="64000:65536" // 256MB Burst  
PRIVVMPAGES="128000:131072" // 512MB Burst  
PRIVVMPAGES="256000:262140" // 1024MB Burst

guaranteed is the minimum amount of virtual memory your vps has in a normal situation.  
burst is the amount of memory your server will be able to use if there is enough available...

just multiply to get the values you want.

hope it helps

---

---

Subject: Re: Howto config ve of ram 1GB  
Posted by [powervps](#) on Fri, 07 Dec 2007 23:31:01 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Thx you very much sir i will test them now and get back to you.  
what about

512 MB Ram Guaranteed  
620 MB Burstable Ram

1 Guaranteed Ram  
1500 Burstable Ram

---

---

Subject: Re: Howto config ve of ram 1GB  
Posted by [blunt](#) on Fri, 07 Dec 2007 23:35:40 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

it's just doing the maths...

VMGURPAGES="262144:2147483647" // 1GB Guaranteed

PRIVVMPAGES="384000:393212" // 1,5GB Burst

---

---

Subject: Re: Howto config ve of ram 1GB  
Posted by [powervps](#) on Sat, 08 Dec 2007 00:46:07 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Look what iam geting sir

---

```
[root@vpsvps ~]# vzctl create 101 --config vps.basic --hostname server.xxx.net
Warning: VE config file already exists, will be rewritten with /etc/vz/conf/ve-vps.basic.conf-sample
Private area already exists in /vz/private/101
[root@vpsvps ~]# vzctl start 101
Warning: distribution not specified default used /etc/vz/dists/default
Starting VE ...
vzquota : (warning) block_hard_limit [1153534] < block_current_usage [2934380]
VE is mounted
Setting CPU units: 1000
Configure meminfo: 49152
vzquota : (warning) block_hard_limit [1153434] < block_current_usage [2934380]
VE start in progress...
```

Quote:

```
# Copyright (C) 2000-2007 SWsoft. All rights reserved.
#
# This program is free software; you can redistribute it and/or modify
# it under the terms of the GNU General Public License as published by
# the Free Software Foundation; either version 2 of the License, or
# (at your option) any later version.
#
# This program is distributed in the hope that it will be useful,
# but WITHOUT ANY WARRANTY; without even the implied warranty of
# MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the
# GNU General Public License for more details.
#
# You should have received a copy of the GNU General Public License
# along with this program; if not, write to the Free Software
# Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA
#
```

```
ONBOOT="yes"
```

```
# UBC parameters (in form of barrier:limit)
# Primary parameters
AVNUMPROC="360"
NUMPROC="480"
NUMTCPSOCK="720:720"
NUMOTHERSOCK="720:720"
VMGUARPAGES="131072:2147483647"
# Secondary parameters
KMEMSIZE="22111846:22754099"
TCPSNDBUF="319488:524288"
TCPRCVBUF="3440640:5406720"
OTHERSOCKBUF="135168:237568"
```

```
DGRAMRCVBUF="524288:524288"
OOMGUARPAGES="1725:2147483647"
# Auxiliary parameters
LOCKEDPAGES="1024:1024"
SHMPAGES="512:512"
PRIVVMPAGES="256000:262140"
NUMFILE="18624"
NUMFLOCK="396:412"
NUMPTY="32:32"
NUMSIGINFO="512:512"
DCACHESIZE="6819840:7249920"
```

```
PHYSPAGES="0:2147483647"
NUMIPTENT="256:256"
```

```
# Disk quota parameters (in form of softlimit:hardlimit)
DISKSPACE="512000:512000"
DISKINODES="80000:88000"
QUOTATIME="0"
```

```
# CPU fair sheduler parameter
CPUUNITS="1000"
```

---

Subject: Re: Howto config ve of ram 1GB  
Posted by [blunt](#) on Sat, 08 Dec 2007 00:50:59 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Well here is a little tutorial on how to create a VPS:

```
#change to the dir where you have your templates
cd /var/lib/vz/template/cache
```

```
#get the template from the openvz site
wget http://download.openvz.org/template/precreated/[filename]
# create with the template you have downloaded
vzctl create [number] --ostemplate debian-3.1-i386-minimal --config vps.basic
# set onboot to boot the VPS on server boot
vzctl set [number] --onboot yes --save
# set vps hostname
vzctl set [number] --hostname hostname.org --save
#set ip
vzctl set [number] --ipadd 192.168.1.130 --save
#set number of sockets (may not be needed)
vzctl set [number] --numothersock 120 --save
#set the ip of a dns server (local or on the internet)
```

```
vzctl set [number] --nameserver 192.168.1.130 --save
# start vps
vzctl start [number]
#set root password
vzctl exec [number] passwd
```

hope this helps

---

---

Subject: Re: Howto config ve of ram 1GB  
Posted by [powervps](#) on Sat, 08 Dec 2007 01:15:09 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

I will try and get back to you but thx you very much it is very esay

what it is bedst way for create --config vps  
Current CPU utilization: 1000  
Power of the node: 808993

```
VMGUARPAGES="32768:2147483647" // 128MB Guaranteed
PRIVVMPAGES="64000:65536" // 256MB Burst
```

```
VMGUARPAGES="65536:2147483647" // 256MB Guaranteed
PRIVVMPAGES="128000:131072" // 512MB Burst
```

```
VMGUARPAGES="131072:2147483647" // 512MB Guaranteed
PRIVVMPAGES="256000:262140" // 1024MB Burst
```

```
VMGUARPAGES="262144:2147483647" // 1GB Guaranteed
PRIVVMPAGES="384000:393212" // 1,5GB Burst
```

Thx you for your time....

---

---

Subject: Re: Howto config ve of ram 1GB  
Posted by [SoftDux](#) on Sat, 12 Apr 2008 03:33:48 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

powervps wrote on Sat, 08 December 2007 03:15l will try and get back to you but thx you very much it is very esay

what it is bedst way for create --config vps  
Current CPU utilization: 1000

Power of the node: 808993

```
VMGUARPAGES="32768:2147483647" // 128MB Guaranteed  
PRIVVMPAGES="64000:65536" // 256MB Burst
```

```
VMGUARPAGES="65536:2147483647" // 256MB Guaranteed  
PRIVVMPAGES="128000:131072" // 512MB Burst
```

```
VMGUARPAGES="131072:2147483647" // 512MB Guaranteed  
PRIVVMPAGES="256000:262140" // 1024MB Burst
```

```
VMGUARPAGES="262144:2147483647" // 1GB Guaranteed  
PRIVVMPAGES="384000:393212" // 1,5GB Burst
```

Thx you for your time....

Hi powervps

Can you please explain to me how you got the figures?  
I want to set a VPS with 512MB guaranteed RAM, and 1024 burst.

So, I used your example, but free -m shows me something odd:

```
[root@gandalf ~]# vzctl set 1001 --privvmpages=256000:262140 --save  
UB limits were set succesefully  
Saved parameters for VE 1001  
[root@gandalf ~]# vzctl set 1001 --vmguarpages=131072:2147483647 --save  
UB limits were set succesefully  
Saved parameters for VE 1001  
[root@gandalf ~]# vzctl restart 1001  
Restarting VE  
Stopping VE ...  
VE was stopped  
VE is unmounted  
Starting VE ...  
VE is mounted  
Setting CPU units: 1000  
Configure meminfo: 256000  
Set hostname: vps03.softdux.com  
File resolv.conf was modified  
VE start in progress...  
[root@gandalf ~]# vzctl exec 1001 free -m  
      total      used      free  shared  buffers  cached
```

Mem:	1000	171	828	0	0	0
-/+ buffers/cache:		171	828			
Swap:	0	0	0			

Why does the total say 1000, and not 1024, or for that matter 512?

---

---

Subject: Re: Howto config ve of ram 1GB  
Posted by [blunt](#) on Sat, 12 Apr 2008 09:59:11 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

You used these values:

```
VMGUARPAGES="131072:2147483647" // 512MB Guaranteed  
PRIVVMPAGES="256000:262140" // 1024MB Burst
```

free -m shows you the soft limit on burstable ram, which is 256000 (1000MB). The hard limit, the one which you cannot pass is the hard limit (262140 - 1024MB). If you wish, you can set the soft limit equal to the hard limit, both with 262140, and free should say it has 1024MB. free will never show 512MB of ram, unless your hardware node is crowded and there is not enough space for everyone.

Hope this helps.

---

---

Subject: Re: Howto config ve of ram 1GB  
Posted by [SoftDux](#) on Sat, 12 Apr 2008 10:58:46 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

ok, that makes sense.

So, If I sell a VPS with 512 gauranteed & 1024 burst, the user will see 1000MB when he uses free -m to check the memory, or even in cPanel's "Server Information" - can / does this cause a problem?

---

---

Subject: Re: Howto config ve of ram 1GB  
Posted by [blunt](#) on Sat, 12 Apr 2008 23:21:25 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

that is up to your clients...

If you want to avoid problems, just set the soft and hard limit to the hard limit values, and the users will see the 1024MB instead of the 1000MB

---