
Subject: VE login via normal user on HN
Posted by [onegwr](#) on Wed, 19 Mar 2008 22:27:42 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hi all,

* I would like to login as a normal user 'vps101' on the HN and would like to get in a situation like you get after typing "vzctl enter 101". Syncing the password would be nice but is not needed.

* Putting "/usr/sbin/vzctl enter 101" as the shell in /etc/passwd did not did the trick for me.

* I have this trick in a hosted vz environment, so I know it's possible, but I'm unable to replicate it...

any suggestions?

thanks,

Oneg

Subject: Re: VE login via normal user on HN
Posted by [maratrus](#) on Fri, 21 Mar 2008 15:12:11 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hi,

1. Put /bin/bash for user vps101 in /etc/passwd file.
 2. You can add appropriate record to vps101's .bashrc file. Something like that "/usr/sbin/vzctl enter 102" but keep in mind that you need permission to open /dev/vzctl so you need something like that "sudo /usr/sbin/vzctl enter 102"
-

Subject: Re: VE login via normal user on HN
Posted by [onegwr](#) on Fri, 21 Mar 2008 21:54:57 GMT
[View Forum Message](#) <> [Reply to Message](#)

Perfect! That did the trick!

in /home/vps101/.basrc I've added:

```
sudo /usr/sbin/vzctl enter 101
```

exitexit was added to get logged-out after logging out of the VE...

via visudo I've added:

```
vps101  ALL=/usr/sbin/vzctl enter 101
```

Thank you for the advice!

Oneg
