

---

Subject: fuse can not be used in containers after fuse-2.7.3 is installed in Hardware Node

Posted by [efishing](#) on Sun, 27 Apr 2008 11:32:19 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

I install fuse 2.7.3 with kernel module in CentOS 5. FUSE functions well in Hardware Node, but in container, I use "cat /proc/filesystems", and I can not find fuse and fusectl, so I can't mount fuse file system in container. If I install fuse 2.7.3 without kernel module, there is no problem.

---

---

Subject: Re: fuse can not be used in containers after fuse-2.7.3 is installed in Hardware Node

Posted by [maratrus](#) on Mon, 28 Apr 2008 10:01:27 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hello,

1. What kernel do you use? ("uname -a")
2. Could you please specify what does it mean

Quote:

If I install fuse 2.7.3 without kernel module

3. Have you restarted your CT after you'd loaded fuse module on HN.

Thank You!

---

---

Subject: Re: fuse can not be used in containers after fuse-2.7.3 is installed in Hardware Node

Posted by [efishing](#) on Mon, 28 Apr 2008 13:40:44 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

I want to use a FUSE file system "GlusterFS"(www.glusterfs.org) in container. The developers of glusterfs recommend to use a patched fuse module, but I cannot use glusterfs in container after I installed their rpm packages, so I decided to install original FUSE first.

My running kernel was downloaded from this website: 2.6.18-53.1.13.el5.028stab053.10, x86\_64, smp

OS: CentOS 5.1.

Before I install fuse 2.7.3, use:

```
vzctl exec <ctid> cat /proc/filesystems
```

the result is :

ext2

ext3

nodev rpc\_pipefs

nodev autofs

---

```
nodev proc
nodev sysfs
nodev tmpfs
nodev devpts
nodev fusectl
nodev fuse
```

I download fuse 2.7.3 from fuse.sourceforge.net, then:

```
./configure --prefix=/usr --enable-kernel-module
make
make install
ldconfig
rmmod fuse
modprobe fuse
```

I restart the container, execute:

```
vzctl exec <ctid> cat /proc/filesystems
```

the result is :

```
    ext2
    ext3
nodev rpc_pipefs
nodev autofs
nodev proc
nodev sysfs
nodev tmpfs
nodev devpts
```

fuse module is not loaded in the container, so I can't use FUSE in containers. Rebooting the HN can not solve the problem.

---

---

Subject: Re: fuse can not be used in containers after fuse-2.7.3 is installed in Hardware Node

Posted by [TheWiseOne](#) on Thu, 01 May 2008 16:09:03 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

I'm gonna bet it's not the version, but the fact that the custom-compiled fuse module is not virtualized like the one included with the OpenVZ kernel.

---