
Subject: Using veth device, why venet0 still generating?

Posted by [suaz](#) on Mon, 19 May 2008 10:15:13 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi,

first of all :

linux 2.6.18 kernel x86_64

028stab053 patch and kernel configuration

vzctl 3.0.22-1dso1

vzquota 3.0.11-1dso1

OS : debian etch

VEs : all running debian (hope i forgot nothing)

Here's my problem :

I'm working with veth device instead of venet. All my VEs have a config file who look like this :

```
ONBOOT="yes"
```

```
# UBC parameters (in form of barrier:limit)
```

```
# Primary parameters
```

```
NUMPROC="100:100"
```

```
NUMTCPSOCK="360:360"
```

```
NUMOTHERSOCK="360:360"
```

```
VMGUARPAGES="10240:9223372036854775807"
```

```
# Secondary parameters
```

```
KMEMSIZE="6144000:6785400"
```

```
TCPSNDBUF="1720320:2703360"
```

```
TCPRCVBUF="1720320:2703360"
```

```
OTHERSOCKBUF="1126080:2097152"
```

```
DGRAMRCVBUF="262144:262144"
```

```
OOMGUARPAGES="26112:9223372036854775807"
```

```
PRIVVMPAGES="10240:11240"
```

```
# Auxiliary parameters
```

```
LOCKEDPAGES="256:256"
```

```
SHMPAGES="21504:21504"
```

```
PHYSPAGES="0:9223372036854775807"
```

```
NUMFILE="9312:9312"
```

```
NUMFLOCK="188:206"
```

```
NUMPTY="16:16"
```

```
NUMSIGINFO="256:256"
```

```
DCACHESIZE="3409920:3624960"
```

```
#Helper values
```

```
AVNUMPROC="50:50"
```

```
NUMIPTENT="200:200"
```

```
# Disk quota parameters (in form of softlimit:hardlimit)
```

```
DISKSPACE="1048576:1153024"  
DISKINODES="200000:220000"  
QUOTATIME="0"
```

```
# CPU fair sheduler parameter  
CPUUNITS="1000"
```

```
VE_ROOT="/var/lib/vz/root/$VEID"  
VE_PRIVATE="/var/lib/vz/private/$VEID"  
OSTEMPLATE="debian-4.0-test"  
ORIGIN_SAMPLE="vps.basic"  
NAMESERVER="91.121.126.131"  
DEVICES="c:10:200:rw "  
CAPABILITY="NET_ADMIN:on "  
#NETIF="ifname=eth0,mac=00:0C:29:85:E5:63,host_ifname=veth101.0,host_mac=00:0C:29:E5:7  
E:3E"
```

```
NETIF="ifname=eth0,mac=00:0C:29:05:76:28,host_ifname=veth1005.0,host_mac=00:0C:29:5C:E  
B:3C"
```

eth0 is the interface inside the VE and vethx.0 is the one on the HN.

As you can see, there's no sign of any IP_ADDRESS field in this config file as it's supposed to be regarding to this howto : http://wiki.openvz.org/Virtual_Ethernet_device in " Making a veth-device persistent" section.

But when i start vz, all my containers are well created but with venet0 device inside and on the HN.

I forgot to say that i also patched the kernel with the patch given in this topic : <http://forum.openvz.org/index.php?t=msg&goto=1993> but it doesn't have anything to do with venet device (i think...).

If i made myself clear, does anyone has any idea concerning this trouble?
Thank you very much for your answers

Subject: Re: Using veth device, why venet0 still generating?

Posted by [suaz](#) on Mon, 19 May 2008 13:01:24 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hum well,

for newbies like me who'd think it's much more complicated than it actually is, i just had to edit the /etc/network/interfaces file and remove the lines concerning venet0...

Thought i'd already done that before and posted... sorry guys.

Then just edit your template.

Subject: Re: Using veth device, why venet0 still generating?

Posted by [maratrus](#) on Mon, 19 May 2008 13:02:52 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hello,

Could you please clarify this statement

Quote:

But when i start vz, all my containers are well created but with venet0 device inside and on the HN.

There is a bug http://bugzilla.openvz.org/show_bug.cgi?id=478

Is this your case or you have another problem?

Subject: Re: Using veth device, why venet0 still generating?

Posted by [suaz](#) on Tue, 20 May 2008 07:46:11 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi,

I tried to follow the steps described in the bug report and i have the same problem.

When i create an IP address, and remove it after and then restart the VE, i have a venet interface coming up.

When i do this, there's a line in the VE conf file that remains :

```
IP_ADDRESS=""
```

and i thought this was the problem.

But then i manually removed this line and restarted the VE... and the same problem appears (venet0 coming up in the VE instead of eth0 configured with the veth as explained in my previous post).

My solution is to remove venet manually from /etc/network/interfaces file and then start on a template generated without this venet interface in this conf file.

I know this will work for me because i won't have to use the vzctl set VEID --ipadd ipadd --save command for any VE after but "happy" to know it's not normal behaviour.

I didn't find any patch (maybe i didn't search well on bugzilla and if yes sorry for that) and since this bug has been reported 2007-02-28 07:09, do you think it will be corrected?

Thanks for your concern

Subject: Re: Using veth device, why venet0 still generating?

Posted by [suaz](#) on Wed, 21 May 2008 22:15:03 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi there

A little up to get any info who could clarify my situation.

Thank you for your help
