
Posted by [Vasyl](#) on Tue, 07 Oct 2008 16:22:14 GMT

[View Forum Message](#) <> [Reply to Message](#)

```
#vzctl --version
```

```
vzctl version 3.0.14
```

```
#cat /etc/vz/conf/600.conf |grep veth
```

```
NETIF=" ifname=eth0,mac=00:30:48:63:C5:28,host_ifname=veth600.0,host  
_mac=00:30:48:63:C5:27 "
```

```
#vzctl restart 600
```

```
# ifconfig | grep veth
```

```
veth600.0 Link encap:Ethernet HWaddr 00:30:48:63:C5:27
```

```
# brctl addif vzbr0 veth600.0
```

```
interface veth600.0 does not exist!
```

```
#vzctl set 600 --netif_add eth0,00:30:48:63:C5:28,veth600.0,00:30:48:63:C5:27 --save
```

```
Configure veth devices: veth600.0
```

```
Saved parameters for VE 600
```

```
# brctl addif vzbr0 veth600.0
```

```
interface veth600.0 does not exist!
```

Posted by [Bobe](#) on Tue, 07 Oct 2008 18:39:08 GMT

[View Forum Message](#) <> [Reply to Message](#)

```
vzctl set 301 --netif_add eth0 --save
```

```
cat /etc/vz/conf/301.conf |grep veth
NETIF=" ifname=eth0,mac=00:18:51:C9:D1:4F,host_ifname=veth301.0,host
_mac=00:18:51:94:EE:C9 "
```

```
brctl addbr br0
brctl addif br0 eth1
ifconfig eth1 0
ifconfig br0 xxx.xxx.xxx.107
ip route add default via xxx.xxx.xxx.97 dev br0
```

```
vzctl start 301
```

```
brctl addif br0 veth301.0
brctl show
vzctl exec 301 ifconfig eth0 xxx.xxx.xxx.106/28
vzctl exec 301 ifconfig venet0 down
vzctl exec 301 ip route del default via 192.0.2.1 dev venet0
vzctl exec 301 ip route add default via xxx.xxx.xxx.97 dev eth0
```

Posted by [Vasyl](#) on Tue, 07 Oct 2008 19:37:45 GMT
[View Forum Message](#) <> [Reply to Message](#)

```
#brctl addbr vzbr0
#brctl addif vzbr0 veth600.0
#ifconfig vzbr0 x.x.x.x up
```

Posted by [Bobe](#) on Tue, 07 Oct 2008 20:02:39 GMT
[View Forum Message](#) <> [Reply to Message](#)

```
ovz-1:~# brctl show
bridge name bridge id STP enabled interfaces
br0 8000.00185194eec9 no eth1
veth301.0
```

```
ovz-1:~# vzctl restart 301
Restarting VE
Stopping VE ...
VE was stopped
VE is unmounted
Starting VE ...
VE is mounted
Setting CPU units: 1000
Configure meminfo: 232771
Set hostname: www.xxx.xx
File resolv.conf was modified
Configure veth devices: veth301.0
VE start in progress...
```

```
ovz-1:~# brctl show
bridge name bridge id STP enabled interfaces
br0 8000.00304890bf9b no eth1
```

```
ovz-1:~# vzctl exec 301 ifconfig
lo    Link encap:Local Loopback
      inet addr:127.0.0.1  Mask:255.0.0.0
      inet6 addr: ::1/128 Scope:Host
      UP LOOPBACK RUNNING  MTU:16436  Metric:1
      RX packets:37 errors:0 dropped:0 overruns:0 frame:0
      TX packets:37 errors:0 dropped:0 overruns:0 carrier:0
      collisions:0 txqueuelen:0
      RX bytes:20477 (19.9 KiB)  TX bytes:20477 (19.9 KiB)
```

```
venet0  Link encap:UNSPEC  HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
      inet addr:127.0.0.1  P-t-P:127.0.0.1  Bcast:0.0.0.0  Mask:255.255.255.255
      UP BROADCAST POINTOPOINT RUNNING NOARP  MTU:1500  Metric:1
      RX packets:0 errors:0 dropped:0 overruns:0 frame:0
      TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
      collisions:0 txqueuelen:0
      RX bytes:0 (0.0 b)  TX bytes:0 (0.0 b)
```

Posted by [Vasyi](#) on Wed, 08 Oct 2008 01:32:47 GMT
[View Forum Message](#) <> [Reply to Message](#)
