

---

Subject: Shutdown sequence

Posted by [proto](#) on Sun, 08 May 2011 23:37:37 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

I have OpenVZ containers running on TOP of a DRBD block device.

Looking at these 2 files:

```
grep chkconfig /etc/init.d/vz
```

```
# chkconfig: 2345 96 88
```

```
grep chkconfig /etc/init.d/drbd
```

```
# chkconfig: 2345 70 08
```

I can see that it is expected to see the shutdown sequence like this:

```
/etc/rc0.d/K08drbd
```

```
/etc/rc0.d/K88vz
```

This seems like an error to me.

K08drbd tries to unmount the filesystems BEFORE K88vz has shutdown the containers.

To me, OpenVZ shutdown should start MUCH earlier, something like this:

```
grep chkconfig /etc/init.d/vz
```

```
# chkconfig: 2345 96 05
```

Any feedback is welcome.

Proto

---