
Subject: Re: Prevent unmount inside VE

Posted by [Vasily Tarasov](#) on Fri, 09 Feb 2007 11:18:31 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hello,

Yes, VE root can do almost everything in VE, including umounting bind-mounted directories.

I offer you the solution I use, but there can be more smart solutions.

The essence of the solution is to make directory, to which bind-mount is produced `_busy_` from VE0. In your case:

```
root@hn:/# mount --bind /mnt/ /vz/root/100/mnt/
root@hn:/# cd /vz/root/100/mnt/    <--- this makes bind-mount busy
root@hn:/# vzctl enter 100
root@ve:/# cat /proc/mounts
simfs / simfs rw 0 0
ext3 /mnt ext3 rw,data=ordered 0 0
root@ve:/# umount /mnt/             <---- doesn't work
umount: /mnt: device is busy
umount: /mnt: device is busy
root@ve:/# exit
```

By various ways it can be automatized.

As concerns redundant information that ``mount`` still shows in your example, this is because it gets information from `/etc/mntab` on HN, which is of course not updated when umounting in VE occurs. This can be prevented by bind-mounting with `-n` option.

HTH,
Vasily
