
Subject: Re: Running X server in VE

Posted by [tabaki](#) on Sun, 05 Aug 2007 10:16:03 GMT

[View Forum Message](#) <> [Reply to Message](#)

in fedora-6 (centos-5) VE:

I install Xvnc-server. Running Xvnc server over GDM.

vzyum XXX install yum

vzyum XXX install gdm

may be installing by dependence udev, it`s very bad, need remove it

vzrpm XXX -e udev module-init-tools mkinitrd --nodeps

vzrpm XXX -ihv vzdev-xxx.rpm --nodeps

vzrpm XXX -ihv dummy-xxx.rpm --nodeps

Login in VE.

yum install vnc-server xorg-x11-fonts*

If need KDE or GNOME:

yum groupinstall "GNOME Desktop Environment"

or

yum groupinstall "KDE (K Desktop Environment)"

Modification file /etc/gdm/custom.conf for starting Xvnc server on display 0:

init 5

If not OK, need increase limits UBC-resources, see failcnt.

cat /proc/user_beancounters

Connect to VE trough VNC-client (on Windows or Linux)

Sorry for my english.
