

---

Subject: Re: using cdrom from inside VE

Posted by [Vasily Tarasov](#) on Mon, 14 May 2007 09:36:29 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hello,

1) `--devices b:3:0:r --save`` does not create a device node in `/dev`. It only grants permissions to the device! You can use `--devnodes hda:r --save`` command, which not only grants permissions, but also creates a node.

2) However, if you're using `udev` in VE (just check whether `tmpfs` is mounted on `/dev`, if it is so, then you're using `udev`), you need to create a device node inside VE manually once again:

```
vzctl exec <veid> mknod /dev/hda b 3 0
```

HTH,

Vasily.

---