
Subject: [PATCH ext3/ext4] lost brelse in ext3_read_inode
Posted by [vaverin](#) on Sat, 02 Jun 2007 12:40:13 GMT
[View Forum Message](#) <> [Reply to Message](#)

From: Kirill Korotaev <dev@openvz.org>

One of error path in ext3_read_inode() leaks bh since brelse is forgotten.

Signed-Off-By: Kirill Korotaev <dev@openvz.org>

Acked-by: Vasily Averin <vvvs@sw.ru>

```
diff --git a/fs/ext3/inode.c b/fs/ext3/inode.c
index a6cb617..2a85dde 100644
--- a/fs/ext3/inode.c
+++ b/fs/ext3/inode.c
@@ -2677,8 +2677,10 @@ void ext3_read_inode(struct inode * inode)
 */
 ei->i_extra_isize = le16_to_cpu(raw_inode->i_extra_isize);
 if (EXT3_GOOD_OLD_INODE_SIZE + ei->i_extra_isize >
-   EXT3_INODE_SIZE(inode->i_sb))
+   EXT3_INODE_SIZE(inode->i_sb)) {
+   brelse (bh);
+   goto bad_inode;
+ }
 if (ei->i_extra_isize == 0) {
 /* The extra space is currently unused. Use it. */
 ei->i_extra_isize = sizeof(struct ext3_inode) -
diff --git a/fs/ext4/inode.c b/fs/ext4/inode.c
index b34182b..0cd7bc4 100644
--- a/fs/ext4/inode.c
+++ b/fs/ext4/inode.c
@@ -2673,8 +2673,10 @@ void ext4_read_inode(struct inode * inode)
 */
 ei->i_extra_isize = le16_to_cpu(raw_inode->i_extra_isize);
 if (EXT4_GOOD_OLD_INODE_SIZE + ei->i_extra_isize >
-   EXT4_INODE_SIZE(inode->i_sb))
+   EXT4_INODE_SIZE(inode->i_sb)) {
+   brelse (bh);
+   goto bad_inode;
+ }
 if (ei->i_extra_isize == 0) {
 /* The extra space is currently unused. Use it. */
 ei->i_extra_isize = sizeof(struct ext4_inode) -
```
