

---

Subject: Re: Static ARP setting in VM

Posted by [kir](#) on Wed, 23 May 2007 12:37:34 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

In case you are using venet networking for a VE (venet is default), host system acts as a router, and VE has a macless venet device -- so there is no arp and you can not add arp entries.

I'm not sure what you try to achieve, but you can either add arp entry on the host system, or try using veth (see <http://wiki.openvz.org/Veth>), which is bridged (as opposed to routed) networking for a VE with a mac address.

Last way is to use real ethernet device (vzctl set --netdev\_add)

---