
Subject: Re: Migration error - Quota is not running
Posted by [Andrey Mirkin](#) on Wed, 20 Jun 2007 11:29:52 GMT
[View Forum Message](#) <> [Reply to Message](#)

After some investigation on your node I have found that some iptables modules are not loaded on destination node.

On source node in /etc/vz/vz.conf we have:

```
IPTABLES="ipt_REJECT ipt_tos ipt_TOS ipt_LOG ip_conntrack ipt_limit ipt_multiport iptable_filter  
iptables_mangle ipt_TCPMSS ipt_tcpmss ipt_ttl ipt_length ipt_state iptable_nat ip_nat_ftp"
```

On destination node we have:

```
IPTABLES="ip_tables ipt_REJECT ipt_tos ipt_limit ipt_multiport iptable_filter iptable_mangle  
ipt_TCPMSS ipt_tcpmss ipt_ttl ipt_length"
```

After changing this value on dst node and restarting vz service I was able to migrate this VE.
