
Subject: Re: Dual NIC Setup

Posted by [vaverin](#) on Mon, 03 Sep 2007 07:21:46 GMT

[View Forum Message](#) <> [Reply to Message](#)

By default VE uses source IP for outgoing packets taken from first venet interface. In your case it is public IP.

It looks you want to change this behaviour and set private source IP if VE accessed private network:

```
ip route add to 10.0.0.0/8 src 10.x.y.z dev venet0
```

and set public source IP for any other connections

```
ip route add default src 74.86.x.y dev venet0
```

update: I would note -- you should add these rules inside your VEs

Thank you,
Vasily Averin
