

---

Subject: Re: Re: The problem of iptables on FC4  
Posted by [kir](#) on Mon, 20 Feb 2006 07:59:02 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Kirill Korotaev wrote:

>> I wrote modprobe to /etc/init.d/iptables file and reboot.  
>> but, not accept.  
>  
> probably it is executed too late. And ip\_conntrack module is loaded  
> somewhere else, maybe indirectly via loading some other  
> conntrack-dependant module.

Let me give you my \$0.02 :)

To provide any parameter on module loading, the best place would be /etc/modprobe.conf file. In our case, to enable connection tracking for the host system, add the following line to /etc/modprobe.conf:

```
options ip_conntrack ip_conntrack_enable_ve0=1
```

After that, you need to reload the module, i.e.

```
modprobe -r ip_conntrack
```

(check that module was really unloaded: `/sbin/lsmmod | grep conntr`)

```
modprobe ip_conntrack
```

---