

---

Subject: Re: Ubuntu Gutsy Gibson Template Cache  
Posted by [ckpeter](#) on Wed, 24 Oct 2007 16:06:34 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

I ran a strace:

```
[root@host ~]# strace -f -o vz.out vzctl --verbose start 3001
Starting VE ...
VE is mounted
Adding IP address(es): x.x.x.x
Running VE script: /etc/vz/dists/scripts/debian-add_ip.sh
[ Process PID=18853 runs in 32 bit mode. ]
[ Process PID=18852 runs in 64 bit mode. ]
Execution timeout expired
ptrace: umoven: Input/output error
Got signal 15
Setting CPU units: 1000
Configure meminfo: 204800
Running VE script: /etc/vz/dists/scripts/set_dns.sh
[ Process PID=19118 runs in 32 bit mode. ]
[ Process PID=19117 runs in 64 bit mode. ]
[ Process PID=19118 runs in 32 bit mode. ]
[ Process PID=19117 runs in 64 bit mode. ]
[ Process PID=19118 runs in 32 bit mode. ]
[ Process PID=19117 runs in 64 bit mode. ]
Execution timeout expired
ptrace: umoven: Input/output error
Got signal 15
File resolv.conf was modified
VE start in progress...
[ Process PID=18826 runs in 32 bit mode. ]
```

At this point I control-C to get out of the process.

The trace file reveals that it is choking on /dev/console:

```
18826 open("/dev/console", O_WRONLY|O_NOCTTY) = -1 EACCES (Permission denied)
18826 read(3, 0xbff6f20b, 1) = -1 EAGAIN (Resource temporarily unavailable)
18826 waitid(P_ALL, 0, {}, WNOHANG|WEXITED|WNOWAIT, NULL) = 0
18826 time(NULL) = 1193241775
18826 select(4, [0 3], [], [], NULL) = 1 (in [0])
18826 getsockname(0, 0xbff6ef04, [112]) = -1 ENOTSOCK (Socket operation on non-socket)
18826 recvmsg(0, 0xbff6efa8, MSG_PEEK) = -1 ENOTSOCK (Socket operation on non-socket)
18826 time(NULL) = 1193241775
18826 stat64(0xb7fb83a6, 0xbff6ebe8) = 0
18826 stat64(0xb7fb83a6, 0xbff6eaa0) = 0
```

```
18826 stat64(0xb7fb83a6, 0xbff6eaa0) = 0
18826 socket(PF_FILE, SOCK_DGRAM, 0) = 1
18826 fcntl64(1, F_SETFD, FD_CLOEXEC) = 0
18826 connect(1, {sa_family=AF_FILE, path="/dev/log"}, 110) = -1 ENOENT (No such file or
directory)
18826 close(1) = 0
18826 open("/dev/console", O_WRONLY|O_NOCTTY) = -1 EACCES (Permission denied)
18826 read(3, 0xbff6f20b, 1) = -1 EAGAIN
```

The preceding output repeats over and over.

---