
Subject: Re: Access to private and public IP in VPS
Posted by [Frederik](#) on Wed, 14 Nov 2007 14:01:15 GMT
[View Forum Message](#) <> [Reply to Message](#)

On Wed, 14 Nov 2007 10:51:48 +0100, Arjan Schrijver wrote:

> I actually did this a few days ago.
> Just add both the public and the private IP address to the VE using
> these commands (don't use veth interfaces):
>
> HN# vzctl set 100 --ipadd [publicip] --save HN# vzctl set 100 --ipadd
> [privateip] --save
>
> In the VE you should now have two ethernet devices: venet0 and venet0:1
> To make it actually work, you have to add routes inside the VE to the
> network that isn't available using the default route:
>
> VE# route add -net [privatenetwork] netmask 255.255.255.0 gw [privateip]

Thank you. The above route command was the missing link in my setup. I already tried using the private IP of the HN as the gw for that network, but that did not work. Using the VEs own private IP as the gw did indeed the trick.

--
Frederik
