
Subject: Re: post-start and stop scripts

Posted by [Jakob Goldbach](#) on Wed, 09 Jan 2008 20:09:48 GMT

[View Forum Message](#) <> [Reply to Message](#)

On Wed, 2008-01-09 at 13:07 +0100, Thorsten Schifferdecker wrote:

>

> please read the OpenVZ User Guide, at page 88 "OpenVZ Action Scripts".

>

Yes! - sorry for not seeing this on first read..

Bind mounting works fine during start, but umounting on stop fails.
umount just boils down to a 'umount -v <mountpt>'.

See transcript and full mount/umount script below.

What am I missing here ?

I'm using 2.6.18-ovz-028stab051.1 (x86_64) with vzctl version
3.0.22-1dsol

/Jakob

```
HN:~# vzctl start 222
```

```
Starting VE ...
```

```
/bin/mount -v --bind /mnt/test /var/lib/vz/root/222/mnt/bindmpt
```

```
/mnt/test on /var/lib/vz/root/222/mnt/bindmpt type none (rw,bind)
```

```
VE is mounted
```

```
Adding IP address(es): 172.16.4.9
```

```
Setting CPU units: 1000
```

```
Configure meminfo: 35000
```

```
Set hostname: test1
```

```
VE start in progress...
```

```
HN:~# mount
```

```
[snip]
```

```
/mnt/test on /var/lib/vz/root/222/mnt/bindmpt type none (rw,bind)
```

```
HN:~# vzctl stop 222
```

```
Stopping VE ...
```

```
VE was stopped
```

```
/bin/umount -v /var/lib/vz/root/222/mnt/bindmpt
```

```
could not umount /var/lib/vz/root/222/mnt/bindmpt - trying /mnt/test  
instead
```

```
umount: /mnt/test: not mounted
could not umount /var/lib/vz/root/222/mnt/bindmpt - trying /mnt/test
instead
umount: /mnt/test: not mounted
Error executing umount script /etc/vz/conf/222.umount
```

```
HN:~# vzlist -a
  VEID   NPROC STATUS IP_ADDR  HOSTNAME
  222     - mounted 172.16.4.9 test1
```
