
Subject: Patch to correct order of unmounting in vzctl
Posted by [Griffon26](#) on Fri, 28 Apr 2006 22:53:04 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hi guys,

The attached patch corrects the unmount order in vzctl to follow the description of it in the user manual (VPS amount before global amount instead of the other way around). It applies to vzctl-3.0.0.8.

Regards,
Maurice.

--

Maurice van der Pot

Gentoo Linux Developer griffon26@gentoo.org <http://www.gentoo.org>
Creator of BiteMe! griffon26@kfk4ever.com <http://www.kfk4ever.com>

```
diff -ruN vzctl-3.0.0-8/src/lib/fs.c vzctl-3.0.0-8-patched/src/lib/fs.c
--- vzctl-3.0.0-8/src/lib/fs.c 2006-04-19 14:19:06.000000000 +0200
+++ vzctl-3.0.0-8-patched/src/lib/fs.c 2006-04-28 23:51:09.843033500 +0200
@@ -179,16 +179,16 @@
     return 0;
 }
 if (!(skip & SKIP_ACTION_SCRIPT)) {
- snprintf(buf, sizeof(buf), "%svps.%s", VPS_CONF_DIR,
- UMount_PREFIX);
+ snprintf(buf, sizeof(buf), "%s%d.%s", VPS_CONF_DIR,
+ veid, UMount_PREFIX);
     for (i = 0; i < 2; i++) {
         if (run_pre_script(veid, buf)) {
             logger(0, 0, "Error executing umount script %s",
                 buf);
             return VZ_ACTIONSRIPT_ERROR;
         }
- snprintf(buf, sizeof(buf), "%s%d.%s", VPS_CONF_DIR,
- veid, UMount_PREFIX);
+ snprintf(buf, sizeof(buf), "%svps.%s", VPS_CONF_DIR,
+ UMount_PREFIX);
     }
 }
 if (!(ret = fsumount(veid, root)))
```
