
Subject: Re: Host firewall

Posted by [Vasily Tarasov](#) on Thu, 11 May 2006 08:42:26 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hello, the reason of this issue is that VPS and Host talk through interface venet0. So you have to tune iptables to work properly with this interface too.

Here is a small patch for your script.

You can easily change it if you wish some slightly other behaviour.

```
--- firewall.sh.back 2006-05-10 19:23:09.000000000 +0400
+++ firewall.sh 2006-05-10 20:40:00.000000000 +0400
@@ -97,6 +97,16 @@ $IPT -A INPUT -i $INTERFACE -p icmp -s $
```

```
$IPT -A OUTPUT -o $INTERFACE -p icmp -s $IPADDR \
--icmp-type echo-reply -d $LAN -j ACCEPT
```

```
+
```

```
+# Allow host to ping VPS
```

```
+VENET="venet0"
```

```
+VPSIP="192.168.0.102"
```

```
+$IPT -A OUTPUT -o $VENET -p icmp -s $IPADDR \
```

```
+-icmp-type echo-request -d $VPSIP -j ACCEPT
```

```
+# Allow host to receive ping from VPS
```

```
+$IPT -A INPUT -i $VENET -p icmp -s $VPSIP \
```

```
+-icmp-type echo-request -d $IPADDR -j ACCEPT
```

```
+
```

```
# =====
```

```
# Allow limited access to host
```

Good luck.
