
Subject: Re: can access vps from server not from network
Posted by [abhishek jain](#) on Wed, 17 May 2006 02:02:58 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hi,
Just to add to that,
I get the following error while i type /etc/init.d/network restart
[root@server ~]# /etc/init.d/network restart
Shutting down interface venet0: [OK]
Shutting down loopback interface: [OK]
Setting network parameters: net.ipv4.ip_forward = 0
error: unknown error 1 setting key 'net.ipv4.conf.default.rp_filter'
error: unknown error 1 setting key
'net.ipv4.conf.default.accept_source_route'
error: unknown error 1 setting key 'kernel.sysrq'
error: unknown error 1 setting key 'kernel.core_uses_pid'
[FAILED]
Bringing up loopback interface: [OK]
Bringing up interface venet0: [OK]

This Failed line appears.
Can anyone suggest that why does the VPS fails to do network restart.
Thanks,
Abhishek jain

On 5/17/06, abhishek jain <mail@ejain.com> wrote:

>
> Hi,
> No the nameserver does not seem to be the problem , as i have already
> configured that.
> i have already had a entry at /etc/resolv.conf .
> I think the problem like in some setting for the default gateway and like.
> I am not sure,but that seems to be the problem to me, Can anyone suggest
> the right network settings for the same.
> Also the error i get when wget is:
>
> -bash-3.00# wget yahoo.com
> --20:57:42-- http://yahoo.com/
> => `index.html'
> Resolving yahoo.com... failed: Temporary failure in name resolution.
>
> Also this does not seem to be a firewall issue as i have not set up a
> firewall
> Thanks
> --
> Thanks,
> Abhishek jain
>

>

> On 5/17/06, wrote:

>>

>> (1) From inside VE, you do not need to configure any sysctl parameters.

>>

>> (2) Probably the reason why you can not reach any hosts from inside VE

>> is you forgot to set VE's nameserver. Please do the following:

>> a. on the host system, check your nameserver(s) IP address(es):

>> # grep nameserver /etc/hosts

>> It should print one or more lines in the form

>> nameserver x.x.x.x

>> where x.x.x.x is an IP address.

>> b. Set that (those) address(es) to be VE's nameserver(s):

>> # vzctl set VEID --nameserver x.x.x.x [--nameserver y.y.y.y] --save

>>

>> In fact, just one nameserver should be sufficient.

>>

>> (3) For the next time, please provide more details. Here you wrote:

>>

>>> cannot ping or wget anyfile while inside the VPS.

>>

>> It would be great to show some examples here. Say, if nameserver is not

>> set, the error from ping or wget would be like "Temporary failure in

>> name resolution" or "Unable to resolve hostname xxxx.tld". Since you do

>> not give details here, we have to guess.

>>

>> Regards,

>> Kir.

>>

>> abhishek jain wrote:

>>

>>>>On Tue, May 16, 2006 at 08:08:14AM +0530, abhishek jain wrote:

>>>> Hi,

>>>> I add vps via the process listed at quick install guide, i can

>>>> access the

>>>> vps via the server on which it is hosted , but when accessing from

>>>> outside

>>>> using the assigned IP i access the server and not the VPS.

>>>> I can see the ip assigned to VPS in /sbin/ifconfig of the server.

>>>>

>>>>Make sure

>>>>

>>>># sysctl net.ipv4.ip_forward

>>>>

>>>>prints 1. If it doesn't, set it with

>>>>

>>>># sysctl net.ipv4.ip_forward=1

>>>>

> > >>To have it set on every boot you need to tweak a config file depending
> > >>on the distro you're using. E.g. for RedHat-based distros (RHEL,
> > >>Fedora, CentOS) this is /etc/sysctl.conf.
> > >>
> > >>IIRC this is mentioned in the installation guide.
> > >>
> > >>Roman.
> > >>
> > > hi,
> > > Actually the problem solved by deleting the IP from the main system.
> > > Now another problem arised that i can access the VPS from outside but
> > > cannot ping or wget anyfile while inside the VPS.
> > > I see the document and it was written
> > >
> > > sysctl ?w net.ipv4.tcp_ecn=0
> > >
> > > I did this both on the VPS and in the Server still no result.
> > >
> > > Also i get the following error when i start the network while inside
> > > the VPS :
> > >
> > > [root@server ~]# /etc/init.d/network restart
> > > Shutting down interface venet0: [OK]
> > > Shutting down loopback interface: [OK]
> > > Setting network parameters: net.ipv4.ip_forward = 0
> > > error: unknown error 1 setting key 'net.ipv4.conf.default.rp_filter'
> > > error: unknown error 1 setting key
> > > 'net.ipv4.conf.default.accept_source_route'
> > > error: unknown error 1 setting key 'kernel.sysrq'
> > > error: unknown error 1 setting key 'kernel.core_uses_pid'
> > > [FAILED]
> > > Bringing up loopback interface: [OK]
> > > Bringing up interface venet0: [OK]
> > >
> > > This Failed line appears.
> > >
> > > Pl. help,
> > > Thanks,
> > > Abhishek jain
> > >
> > > -----
> > -----
> > >
> >
>
>
