
Subject: Re: VE migration failed: Can not dump VE: d_path is invisible

Posted by [januszzz](#) on Wed, 24 Sep 2008 11:32:38 GMT

[View Forum Message](#) <> [Reply to Message](#)

Well, I didn't have any extra mounts, just plain system with fifos, I found that each of the fifo was stopper for OpenVZ, but...

...but I find OpenVZ migration extremely frustrating now, because this message has gone just after reboot of those machines (HEs)!!

Anyway, I'm having more errors now:

```
vzmigrate -v -r no --online 126.66.64.64 123
```

```
OPT:-v
```

```
OPT:-r
```

```
OPT:--online
```

```
OPT:126.66.64.64
```

```
Starting online migration of VE 123 on 126.66.64.64
```

```
* status: started
```

```
  Loading /etc/vz/vz.conf and /etc/vz/conf/123.conf files
```

```
  Check IPs on destination node: 126.66.64.152
```

```
Preparing remote node
```

```
  Copying config file
```

```
123.conf
```

```
100% 1708  1.7KB/s  00:00
```

```
Saved parameters for VE 123
```

```
/usr/sbin/vzmigrate: line 382: [: missing `']
```

```
  Creating remote VE root dir
```

```
  Creating remote VE private dir
```

```
  VZ disk quota disabled -- skipping quota migration
```

```
Syncing private
```

```
Live migrating VE
```

```
  Suspending VE
```

```
Setting up checkpoint...
```

```
  suspend...
```

```
  get context...
```

```
Checkpointing completed succesfully
```

```
  Dumping VE
```

```
Setting up checkpoint...
```

```
  join context..
```

```
  dump...
```

```
Checkpointing completed succesfully
```

```
  Copying dumpfile
```

```
dump.123
```

```
100% 160MB 11.5MB/s  00:14
```

```
  Syncing private (2nd pass)
```

```
  VZ disk quota disabled -- skipping quota migration
```

```
  Undumping VE
```

```
Restoring VE ...
```

```
Starting VE ...
```


Restoring failed:
Error: do_rst_mm 27294312
Error: rst_mm: -28
Error: make_baby: -28
Error: rst_clone_children
Stopping VE ...
VE start failed
VE was stopped
VE is unmounted
Error: Failed to undump VE
Resuming...
arp send: 126.66.64.152 is detected on another computer : 00:1c:23:27:03:bf
vps-net_add WARNING: arp send -c 1 -w 1 -D -e 126.66.64.152 eth0 FAILED

On the second HN (126.66.64.64) I get
CPT ERR: xxxxxxxxxxxxxx,123 : do_rst_mm xxxxx
rst_mm: -28
make_baby: -28
rst_clone_children

and the like.
