
Subject: Very strange guest network hang
Posted by [pentarh](#) on Wed, 08 Oct 2008 11:15:07 GMT
[View Forum Message](#) <> [Reply to Message](#)

I constantly observe very strange guests hanging on my host machine.

During few days after start, guest OS stops to respond to incoming connections (even SSH).

There is total silence in logs about this. I just notice that suddenly guest disappeared from network.

Then i login to host, and

```
host# vzctl status guest
VEID 100 exist mounted running
```

```
host# vzctl enter guest
entered into VE 100
-bash-3.2#
```

all commands working inside guest, but network is down. All processes excepting my shell are in sleep state.

```
/proc/user_beancounters shows 0 of any failcnt - no limits were reached.
```

The only thing helps - to stop and start guest.

This happens not only on one guest - there are three guests and all of them periodically have network hangs.

What is that?

```
=====My config=====
```

```
Host OS: Centos 5.2 x86_64
```

```
Guests: from official OS templates: centos-5-i386-minimal, centos-5-x86_64-minimal
```

```
Host kernel: 2.6.18-92.1.1.el5.028stab057.2 #1 SMP
```

```
host# cat /proc/vz/version
028stab057
host# vzctl --version
vzctl version 3.0.22
```

Network configuration is standard venet. I use real IP addresses for guests. When creating guest, i remove IP alias from host and add it to guest. There are no firewalls used.

Example of guest config on x86_64:
ONBOOT="yes"

```
# UBC parameters (in form of barrier:limit)
KMEMSIZE="30372700:35372700"
LOCKEDPAGES="256:256"
PRIVVMPAGES="262144:262144"
SHMPAGES="21504:21504"
NUMPROC="512:512"
PHYSPAGES="0:9223372036854775807"
VMGUARPAGES="67584:9223372036854775807"
OOMGUARPAGES="26112:9223372036854775807"
NUMTCPSTOCK="360:360"
NUMFLOCK="188:206"
NUMPTY="16:16"
NUMSIGINFO="256:256"
TCPSNDBUF="1720320:2703360"
TCPRCVBUF="1720320:2703360"
OTHERSOCKBUF="1126080:2097152"
DGRAMRCVBUF="262144:262144"
NUMOTHERSOCK="360:360"
DCACHESIZE="3409920:3624960"
NUMFILE="9312:9312"
AVNUMPROC="180:180"
NUMIPTENT="128:128"
```

```
# Disk quota parameters (in form of softlimit:hardlimit)
DISKSPACE="10485760:20971520"
DISKINODES="200000:220000"
QUOTATIME="0"
```

```
# CPU fair sheduler parameter
CPUUNITS="1000"
```

```
VE_ROOT="/vz/root/$VEID"
VE_PRIVATE="/vz/private/$VEID"
OSTEMPLATE="centos-5-x86_64-minimal"
ORIGIN_SAMPLE="vps.basic"
NAME="blogs"
IP_ADDRESS="x.x.x.x"
HOSTNAME="myguest.com"
NAMESERVER="y.y.y.y"
```
